PyS60 Library Reference

Release 1.3.14 final

17 November 2006

Copyright © 2004-2006 Nokia Corporation.

This is Python for S60 version 1.3.14 final created by Nokia Corporation. Files added by Nokia Corporation are licensed under Apache License Version 2.0. The original software, including modifications of Nokia Corporation therein, is licensed under the applicable license(s) for Python 2.2.2, unless specifically indicated otherwise in the relevant source code file.

See http://www.apache.org/licenses/LICENSE-2.0 and http://www.python.org/2.2.2/license.html

Abstract
The Python for S60 Platform (Python for S60) simplifies application development and provides a scripting solution for the Symbian C++ APIs. This document is for Python for S60 version 1.3.14 final that is based on Python 2.2.2.

CONTENTS

1	1 Introduction			1		
	1.1 Scope			1		
	1.2 Audience					
	1.3 New in Release 1.3.14					
	1.4 Naming Conventions			2		
2	2 API Summary			3		
	2.1 Python Standard Library					
	2.2 Python for S60 Extensions					
	2.3 Third-Party Extensions					
_				_		
3	•			5		
	3.1 Concurrency Aspects					
	3.2 Current S60 Python Script Execution Environment					
	3.3 Standard I/O Streams					
	3.4 Usage of Unicode					
	3.5 Date and Time					
	3.6 Sharing Native Resources between Threads					
	3.7 Scalable User Interface					
	3.8 Error Handling					
	3.9 Limitations and Areas of Development			7		
4	4 Operating System Services and Information	Operating System Services and Information				
	4.1 e32 — A Symbian OS related services package			9		
	4.2 sysinfo — Access to system information			11		
5	5 User Interface and Graphics			13		
_	5.1 appuifw — Interface to the S60 GUI framework					
	5.2 graphics — A graphics related services package					
	5.3 camera — Interface for taking photographs					
	5.4 keycapture — Interface for global capturing of key					
	5.5 topwindow — Interface for creating windows that ar					
	•		1	* *		
6				37		
	6.1 audio — An audio related services package					
	6.2 telephone — Telephone services					
	6.3 messaging — A messaging services package					
	6.4 inbox — Interface to device inbox					
	6.5 location — GSM location information			40		
7	7 Data Management			41		
	7.1 contacts — A contacts related services package					
	7.2 calendar — Access to calendar related services					
	7.3 calendar for EKA2 — Access to calendar related so					

	7.4	e32db — Interface to the Symbian native DB	55
	7.5	e32dbm — DBM implemented using the Symbian native DBMS	57
8	Stan	dard Library Support and Extensions	61
	8.1	Support for Python Standard Library	61
	8.2	Extensions to Standard Library Modules	62
9	Exte	ending and Embedding	65
	9.1	Python/C API Extensions	65
	9.2	Extending Python for S60	66
10	Tern	ns and Abbreviations	69
A	Rep	orting Bugs	73
\mathbf{M}	odule	e Index	7 5
In	dex		77

Introduction

The Python for S60 Platform (Python for S60) simplifies application development and provides a scripting solution for the Symbian C++ APIs. This document is for Python for S60 release 1.3.13 that is based on Python 2.2.2.

The documentation for Python for S60 includes three documents:

- Getting Started with Python for S60 Platform [5] contains information on how to install Python for S60 and how to write your first program.
- This document contains API and other reference material.
- Programming with Python for S60 Platform [6] contains code examples and programming patterns for S60 devices that can be used as a basis for programs.

Python for S60 as installed on a S60 device consists of:

- Python execution environment, which is visible in the application menu of the device and has been written in Python on top of Python for S60 Platform (see S60 SDK documentation [4])
- Python interpreter DLL
- Standard and proprietary Python library modules
- \bullet S60 UI application framework adaptation component (a DLL) that connects the scripting domain components to the S60 UI
- Python Installer program for installing Python files on the device, which consists of:
 - Recognizer plug-in
 - Symbian application written in Python

The Python for S60 developer discussion board [9] on the Forum Nokia Web site is a useful resource for finding out information on specific topics concerning Python for S60. You are welcome to give feedback or ask questions about Python for S60 through this discussion board.

1.1 Scope

This document includes the information required by developers to create applications that use Python for S60, and some advice on extending the platform.

1.2 Audience

This guide is intended for developers looking to create programs that use the native features and resources of the S60 phones. The reader should be familiar with the Python programming language (http://www.python.org/) and the basics of using Python for S60 (see Getting Started with Python for S60 Platform [5]).

1.3 New in Release 1.3.14

This section lists the updates in this document since release 1.3.8.

- Section 5.4, keycapture Module has been added.
- Section 5.5, topwindow Module has been added.
- Section 7.3, calendar Module for EKA2 has been added.
- Section 5.5, topwindow Module has been added.
- Method signal_strength for Section 4.2, sysinfo module has been added.
- Method say for Section 6.1, audio module has been added.

1.4 Naming Conventions

Most names of the type ESomething typically indicate a constant defined by the Symbian SDK. More information about these constants can be found in the Symbian SDK documentation.

API Summary

All built-in object types of the Python language are supported in the S60 environment. The rest of the programming interfaces are implemented by various library modules as summarized in this chapter.

2.1 Python Standard Library

Python for S60 platform distribution does not include all of the Python's standard and optional library modules to save storage space in the phone. Nevertheless, many of the excluded modules also work in the S60 Python environment without any modifications. Some modules are included in the SDK version but not installed in the phone. For a summary of supported library modules, see Chapter 8.

When Python, available at http://www.python.org/, is installed on a PC, the library modules are by edefault located in '\Python22\Lib' on Windows and in '\/usr/\lib/\python2.2' on Linux. The Python library modules' APIs are documented in [1].

Python for S60 extends some standard modules. These extensions are described in this document, see Chapter 8.2.

2.2 Python for \$60 Extensions

There are two kinds of native C++ extensions in the Python for S60 Platform: built-in extensions and dynamically loadable extensions.

2.2.1 Built-in extensions

There are two built-in extensions in the Python for S60 package:

- The e32 extension module is built into the Python interpreter on Symbian OS, and implements interfaces to special Symbian OS Platform services that are not accessible via Python standard library modules.
- The appuifw module for Python for S60 Platform offers UI application framework related Python interfaces.

2.2.2 Dynamically loadable extensions

These dynamically loadable extension modules provide proprietary APIs to S60 Platform's services: graphics (see Chapter 5.2, graphics Module), e32db (see Chapter 7.4, e32db Module), messaging (see Chapter 6.3, messaging Module), inbox (see Chapter 6.4, inbox Module), location (see Chapter 6.5, location Module), sysinfo (see Chapter 4.2, sysinfo Module), camera (see Chapter 5.3, camera Module), audio (see Chapter 6.1, audio Module), telephone (see Chapter 6.2, telephone Module), calendar (see Chapter 7.2, calendar Module), and contacts (see Chapter 7.1, contacts Module).

2.3 Third-Party Extensions

It is also possible to write your own Python extensions. S60 related extensions to Python/C API are described in Chapter 9.1. For some further guidelines on writing extensions in C/C++, see Chapter 9.2. In addition, for an example on porting a simple extension to S60, see [6].

Selected Issues on Python Programming for S60

The following issues must be considered when using Python on S60.

3.1 Concurrency Aspects

The thread that initializes the Python interpreter becomes the main Python thread. This is usually the main thread of a UI application. When an application written in Python launches, the Symbian platform infrastructure creates the main UI thread that starts the Python environment. If a Python program is started as a server with e32.start_server, then the Python main thread is not a UI thread.

It is possible to launch new threads via the services of thread module. Examples of such situations could be to overcome eventual problems with the fixed, relatively small stack size of the main UI application thread; or to perform some background processing while still keeping the UI responsive. These new threads are not allowed to directly manipulate the UI; in other words, they may not use the appuifw module.

Because of the limitations of the Python interpreter's final cleanup, Python applications on the Symbian OS should be designed in such a way that the main thread is the last thread alive.

A facility called active object is used extensively on the Symbian OS to implement co-operative, non-preemptive scheduling within operating system threads. This facility is also utilized with native APIs. A Python programmer is exposed to related concurrency issues particularly in UI programming. Preserving the responsiveness of the UI with the help of active objects needs to be considered when designing the application logic. At the same time it is necessary to take into account the resulting concurrent behavior within the application when active objects are used. While the main execution path of a UI script is blocked in wait for an active object to complete – either explicitly as a result of using e32.Ao_lock, or indirectly within some other Python API implementation – the UI-related callbacks may still get called.

The standard thread.lock cannot normally be used for synchronization in the UI application main thread, as it blocks the UI event handling that takes place in the same thread context. The Symbian active object based synchronization service called e32.Ao_lock has been implemented to overcome this problem. The main thread can wait in this lock, while the UI remains responsive.

Python for S60 tries to minimize the unwanted exposure of a Python programmer to the active objects of the Symbian OS. The programmer may choose to implement the eventual concurrent behavior of the application with normal threads. However, certain active object based facilities are offered as an option in the e32 module.

3.2 Current S60 Python Script Execution Environment

The current options for installing Python scripts to a S60 device are: a stand-alone installation to the device's main application menu, and an installation to a folder hierarchy maintained by the Python

execution environment. For more details on this topic, see Programming with Python for S60 Platform [6]. In the first case the script application is launched via application menu, and it executes in its own process context. The latter case is suitable for development, testing, and trying out new scripts.

The Python execution environment delivered with Python for S60 package has itself been written in Python. It is a collection of scripts that offer an interactive Python console and a possibility to execute scripts located in the directory of the execution environment. Due to this kind of design the scripts are not fully isolated from each other. This means that any changes a script makes in the shared execution environment are visible to other scripts as well. This may be helpful during the development of a script suite, as long as care is taken to avoid unwanted interference between scripts.

For some special issues to consider when writing Python scripts to be run from the current Python execution environment, see Programming with Python for S60 Platform [6]. These include the arrangements for standard output and the maintenance of the Options menu contents.

3.3 Standard I/O Streams

The standard Python I/O streams in the sys module are by default connected to underlying C STDLIB's stdio streams that in turn are terminated by dummy file descriptors. Usually Python scripts set the I/O streams suitably by manipulating them at Python level via sys module interface. The e32 extension module offers a Python interface for attaching to C STDLIB's output streams, but this service is only recommended for debugging purposes. The e32._stdo function takes as its argument the name of the file where C STDLIB's stdout and stderr are to be redirected. This makes it possible to capture the low-level error output when the Python interpreter has detected a fatal error and aborts.

3.4 Usage of Unicode

No changes have been made to the standard library modules with regard to string argument and return value types. S60 extensions generally accept both plain strings and Unicode strings as arguments, but they return only Unicode strings. APIs that take string arguments for the purpose of showing them on the UI expect Unicode strings. Giving something else may result in garbled appearance of the text on the screen.

3.5 Date and Time

Unix time, seconds since January 1, 1970, 00:00:00 UTC (Coordinated Universal Time), is generally used as the time format in the Python for S60 APIs described in this document. The float type is used for storing time values.

3.6 Sharing Native Resources between Threads

Warning: Python for S60 objects that wrap native resources cannot be shared between threads. Trying this can lead to a crash. This is because native resources cannot be shared between native threads. Examples:

- Symbian OS STDLIB implementation has some limitations that are reflected at OS module support (see S60 SDK documentation [4]). For example, STDLIB file descriptors cannot be shared between threads, and for that reason, Python file objects cannot either.
- Sockets as implemented in the S60 version of the socket module.

3.7 Scalable User Interface

Note: S60 2nd Edition FP3 and further releases.

S60 2nd Edition FP3 enables a new feature called scalable user interface. For Python developers scalable user interface is currently visible in new APIs supporting the scalable UI, icon loading, and new screen resolutions. For more information on scalable user interface, see Section 5.1.8, Icon Type of this document, as well as Programming with Python for S60 Platform [6].

3.8 Error Handling

The APIs described in this document may raise any standard Python exceptions. In situations where a Symbian error code is returned, its symbolic name is given as the value parameter of a SymbianError exception.

In case where the functions have nothing special to return, they return None on success.

3.9 Limitations and Areas of Development

Some OS level concepts to which the standard os library module offers an interface do not exist as such in Symbian OS environment. An example of this is the concept of current working directory.

Reference cycle garbage collection is not in use. Because of this, special care needs to be taken to dismantle cyclic references when a Python program exits. This prevents error messages related to native resources that are left open. The problem could be removed by developing support for collection of cyclic garbage or by performing a special cleanup action on interpreter exit. The gc module has been ported to the Symbian OS, and it has been verified to work. However, the current distribution has been built without gc support.

Operating System Services and Information

4.1 e32 — A Symbian OS related services package

The e32 module offers Symbian OS related utilities that are not related to the UI and are not provided by the standard Python library modules.

4.1.1 Module Level Functions

The following free functions - functions that do not belong to any class - are defined in the e32 module:

ao_yield()

Yields to the active scheduler to have ready active objects with priority above normal scheduled for running. This has the effect of flushing the eventual pending UI events. Note that the UI callback code may be run in the context of the thread that performs an ao_yield. For information on active scheduler, see S60 SDK documentation [4].

ao_sleep(interval [, callback])

Sleeps for the given *interval* without blocking the active scheduler. When the optional *callback* is given, the call to ao_sleep returns immediately and the *callback* gets called after *interval*. See also Section 4.1.3, Ao_timer Type.

ao_callgate(wrapped_callable)

Wraps wrapped_callable into returned callable object callgate that can be called in any thread. As a result of a call to callgate, wrapped_callable gets called in the context of the thread that originally created the callgate. Arguments can be given to the call. This is actually a simple wrapping of the Symbian active object facility.

drive_list()

Returns a list of currently visible drives as a list of Unicode strings '<driveletter>:'

file_copy(target_name, source_name)

Copies the file *source_name* to *target_name*. The names must be complete paths.

in_emulator()

Returns 1 if running in an emulator, or 0 if running on a device.

set_home_time(time)

Set the device's time to time (see Section 3.5).

$pys60_version$

A string containing the version number of the Python for S60 and some additional information. Example:

```
>>> import e32
>>> e32.pys60_version
'1.2 final'
```

pys60_version_info

A tuple containing the five components of the Python for S60 version number: major, minor, micro, release tag, and serial. All values except release level are integers; the release tag is a string. A value other than 'final' for the release tag signifies a development release. The pys60_version_info value corresponding to the Python for S60 version 1.2 is (1, 2, 0, 'final', 0).

s60 version info

The SDK version with which this Python was compiled (tuple). The following values are possible:

- •(1, 2) for S60 1st Edition
- •(2, 0) for S60 2nd Edition
- •(2, 6) S60 2nd Edition Feature Pack 2
- •(2, 8) S60 2nd Edition Feature Pack 3

Examples:

```
>>> import e32
>>> e32.pys60_version
'1.2.0 final'
>>> e32.pys60_version_info
(1, 2, 0, 'final', 0)
>>> e32.s60_version_info
(2, 0)
>>>
```

is_ui_thread()

Returns True if the code that calls this function runs in the context of the UI thread; otherwise returns False.

```
start_exe(filename, command [,wait])
```

Launches the native Symbian OS executable *filename* (Unicode) and passes it the *command* string. When *wait* is set, the function synchronously waits for the exit of the executable and returns a value that describes the exit type. Possible values are 0 for normal exit and 2 for abnormal exit.

start_server(filename)

Starts the Python script in file *filename* (Unicode) as a server in its own process. Note that appuifw module is not available to a server script.

4.1.2 Ao_lock Type

class Ao_lock()

Creates an Ao_lock instance. A Symbian active object based synchronization service. This can be used in the main thread without blocking the handling of UI events. The application should not exit while a thread is waiting in Ao_lock. If Ao_lock is called while another wait is in progress, an AssertionError is raised.

Instances of Ao_lock type have the following methods:

wait()

If the lock has already been signaled, returns immediately. Otherwise blocks in wait for the lock to be signaled. Only one waiter is allowed, so you should avoid recursive calls to this service. wait can only be called in the thread that created the lock object. During the wait, other Symbian-active objects are being served, so the UI will not freeze. This may result in the UI callback code being run in the context of the thread that is waiting in Ao_lock. This must be considered when designing the application logic.

signal()

Signals the lock. The waiter is released.

4.1.3 Ao_timer Type

The rationale for the Ao_timer type is that you cannot cancel a pending e32.ao_sleep. This is problematic if e.g. the user exits an application which is sleeping. In this case a panic would occur since the sleep is not cancelled - this is the reason you should avoid using e32.ao_sleep and instead use the Ao_timer with appropriate cancel calls if there is for example a possibility for the user to exit the application during a sleep.

class Ao_timer()

Creates an Ao_timer instance. A Symbian active object based sleeping service. This can be used in the main thread without blocking the handling of UI events. The application should not exit while a thread has a pending after call in Ao_timer. Only one after invocation can be pending at time for each instance of this type.

Instances of Ao_timer type have the following methods:

after(interval [,callback])

Sleeps for the given interval without blocking the active scheduler. When the optional callback is given, the call to after returns immediately and the callback gets called after interval.

cancel()

Cancels a pending after call.

4.2 sysinfo — Access to system information

The sysinfo module offers an API for checking the system information of a S60 mobile device.

Note: The method ring_type is not available for S60 1st Edition.

The sysinfo module has the following functions:

battery()

Returns the current battery level ranging from 0 to 100, with 0 meaning that the battery is empty and 100 meaning that the battery is full. Devices based on Symbian 7.0 or earlier, the battery level is ranged from 0 to 7. If using an emulator, value 0 is always returned.

display_twips()

Returns the width and height of the display in twips. For a definition of a twip, see Chapter 10, Terms and Abbreviations.

display_pixels()

Returns the width and height of the display in pixels.

free_drivespace()

Returns the amount of free space left on the drives in bytes, for example $\{u'C:'100\}$. The keys in the dictionary are the drive letters followed by a colon (:).

imei()

Returns the IMEI code of the device as a Unicode string. If using an emulator, the hardcoded string u'00000000000000' is returned.

max_ramdrive_size()

Returns the maximum size of the RAM drive on the device.

total_ram()

Returns the amount of RAM memory on the device.

free_ram()

Returns the amount of free RAM memory available on the device.

total_rom()

Returns the amount of read-only ROM memory on the device.

ring_type()

Not supported in 1st Edition! Returns the current ringing type as a string, which can be one of the following: 'normal', 'ascending', 'ring_once', 'beep', or 'silent'.

os_version()

Returns the operating system version number of the device as integers. The returned version is defined by a set of three numbers as follows¹:

- •The major version number, ranging from 0 to 127 inclusive
- •The minor version number, ranging from 0 to 99 inclusive
- •The build number, ranging from 0 to 32767 inclusive.

signal()

Returns the current network signal strength ranging from 0 to 7, with 0 meaning no signal and 7 meaning a strong signal.. If using an emulator, value 0 is always returned.

signal_strength()

Returns the current network signal strength in dBm. This is available SDK 2.8 onwards. If using an emulator value 0 is always returned.

sw_version()

Returns the software version as a Unicode string. If using an emulator, the hardcoded string u'emulator' is returned. For example, a software version can be returned as u'V 4.09.1 26-02-04 NHL-10 (c) NMP'.

¹Descriptions for these values are based on information found in S60 SDK documentation [4].

User Interface and Graphics

5.1 appuifw — Interface to the S60 GUI framework

The appuifw module offers an interface to S60 UI application framework. Figure 5.1 provides an overview of the Python for S60 environment for UI application programming.

Note: The services of this interface may only be used in the context of the main thread, that is, the initial thread of a UI application script.

5.1.1 Basics of appuifw Module

Figure 5.2 shows the layout of a S60 application UI in the normal screen mode and a summary of how it relates to the services available at the appuifw API. For alternative layouts, see Figure 5.3.

The main application window may be set up to be occupied by a UI control.

A multi-view application can show the different views as tabs in the navigation pane and react as the users navigate between tabs.

Dialogs always take precedence over the usual UI controls and appear on top of them.

UI controls are implemented as Python types. These types are available:

- Text
- Listbox
- Canvas

UI controls appear on the screen as soon as an instance of the corresponding Python type is created and set to the body field (app.body) of the current application UI.

Form is a versatile dialog implemented as a type.

The Content_handler type facilitates interfacing to other UI applications and common high-level UI components. It is based on the notion that designated handlers can reduce UI application interaction to operations on MIME-type content.

The following dialogs are implemented as functions:

- note
- query
- $\bullet \ \mathtt{multi_query}$
- selection_list
- multi_selection_list




Figure 5.1: Python for S60 UI environment overview




Figure 5.2: The different parts of the screen when using the 'normal' layout




Figure 5.3: UI layouts. left: 'normal', middle: 'large', right: 'full'

• popup_menu

A dialog becomes visible as soon as the corresponding Python function has been called. The function returns with the eventual user input or information on the cancellation of the dialog. Form is an exception; it is shown when its execute method is called.

5.1.2 Softkeys

The softkeys are managed by the underlying S60 Platform. When no dialog is visible, the right softkey is bound to application exit and the left one represents an Options menu. Python for S60 offers an interface for manipulating the menu and for binding the Exit key to a Python-callable object (see Section 5.1.4).

The native code that implements a dialog also manages the softkeys of the dialog, typically OK and Cancel. When the user input needs to be validated before accepting it and dismissing the dialog, it is best to use Form.

5.1.3 Module Level Functions

The following free functions - functions that do not belong to any class - are defined in the appuifw module:

available_fonts()

Returns a list (Unicode) of all fonts available in the device.

```
\verb"query" (label, type" \big[, initial\_value" \big] )
```

Performs a query with a single-field dialog. The prompt is set to *label*, and the type of the dialog is defined by *type*. The value of *type* can be any of the following strings:

- •'text'
- •'code'
- •'number'
- •'date'
- •'time'
- 'query'
- •'float'

The type of the optional *initial_value* parameter and the returned input depend on the value of type:

- •For text fields, ('text', 'code') it is Unicode
- •For number fields, it is numeric
- •For date fields, it is seconds since epoch rounded down to the nearest local midnight

A simple confirmation query and time query take no initial value and return True/None and seconds since local midnight, correspondingly. All queries return None if the users cancel the dialog.

For 'float' query the initial_value setting has no effect.

multi_query(label_1, label_2)

A two-field text (Unicode) input dialog. Returns the inputted values as a 2-tuple. Returns None if the users cancel the dialog.

note(text[, type[, global]])

Displays a note dialog of the chosen type with *text* (Unicode). The default value for *type* is 'info', which is automatically used if *type* is not set. *type* can be one of the following strings: 'error', 'info', or 'conf'.

If global (integer) is any other value than zero a global note is displayed. A global note is displayed even if the Python application calling this function is in background. The same set of types is supported as in standard note.

${\tt popup_menu}(\mathit{list}\big[,\ \mathit{label}\,\big])$

A pop-up menu style dialog. *list* representing the menu contents can be a list of Unicode strings or a list of Unicode string pairs (tuples). The resulting dialog list is then a single-style or a double-style list. A single-style list is shown in full; whereas a double-style list shows the items one at a time. Returns None if the user cancels the operation.

$selection_list(choices[, search_field=0])$

Executes a dialog that allows the users to select a list item and returns the *index* of the chosen item, or None if the selection is cancelled by the users. *choices* is a list of Unicode strings. *search_field* is 0 (disabled) by default and is optional. Setting it to 1 enables a search field (find pane) that facilitates searching for items in long lists. If enabled, the search field appears after you press a letter key.

multi_selection_list(choices[, style='checkbox', search_field=0])

Executes a dialog that allows the users to select multiple list items. Returns a tuple of indexes (a pair of Unicode strings) of the chosen items, or None if the selection is cancelled by the users. choices is a list of Unicode strings. style is an optional string; the default value being 'checkbox'. If 'checkbox' is given, the list will be a checkbox list, where empty checkboxes indicate what items can be marked. The other possible value that can be set for style is 'checkmark'. If 'checkmark' is given, the list will be a markable list, which lists items but does not indicate specifically that items can be selected. To select items on a markable list, use the Navigation key to browse the list and the Edit key to select an item. For example views on checkbox and markable lists, see Figure 5.4. search_field is 0 (disabled) by default and is optional. Setting it to 1 enables a search field (find pane) that facilitates searching for items in long lists. If enabled, the search field is always visible with checkbox lists; with markable lists it appears by pressing a letter key.

Example:

```
tuple = appuifw.multi_selection_list(L, style='checkmark', search_field=1)
```

5.1.4 Application Type

A single implicit instance of this type always exists when appuifw module is present and can be referred to with the name app. New instances cannot be created by a Python program.

class Application

Instances of Application type have the following attributes:



Figure 5.4: Examples of a checkbox list (left) and a markable list (right)

body

The UI control that is visible in the application's main window. Currently either Text, a Listbox object, Canvas, or None.

exit_key_handler

A callable object that is called when the user presses the Exit softkey. Setting exit_key_handler to None sets it back to the default value.

menu

This is a list of the following kinds of items:

- •(title, callback) which creates a regular menu item
- •(title, ((title, callback)[...])) which creates a submenu

title (Unicode) is the name of the item and callback the associated callable object. The maximum allowed number of items in a menu, or items in a submenu, or submenus in a menu is 30.

Example:

screen

The screen area used by an application. See Figure 5.3 for example screens. The appearance of the application on the screen can be affected by setting one of the following values: 'normal', 'large', and 'full'.

Examples:

```
appuifw.app.screen='normal' # (a normal screen with title pane and softkeys)
appuifw.app.screen='large' # (only softkeys visible)
appuifw.app.screen='full' # (a full screen)
```

title

The title the application that is visible in the application's title pane. Must be Unicode.

focus

A callable object that is called with integer as parameter (0 = focus lost, 1 = focus regained) when the application receives focus or it is switched to background. Focus is received e.g. when the application is switched from background to foreground or when the focus is regained from screensaver. Similarly when the screensaver is displayed, focus is lost.

Examples:

```
>>> import appuifw
>>> def cb(fg):
```

```
... if(fg):
... print "foreground"
... else:
... print "background"
...
>>> appuifw.app.focus=cb
>>> # switch to background, following text is printed from callback:
>>> background
>>> # switch to foreground, following text is printed from callback:
>>> foreground
```

Note: An improper callback can cause adverse effects. If you, for example, define a callback which takes no parameters you will receive never-ending TypeError exceptions on the Nokia 6600.

Instances of Application type have the following methods:

```
activate_tab(index)
```

Activates the tab *index* counting from zero.

full_name()

Returns the full name, in Unicode, of the native application in whose context the current Python interpreter session runs.

uid()

Returns the UID, in Unicode, of the native application in whose context the current Python interpreter session runs.

```
set_exit()
```

Requests a graceful exit from the application as soon as the current script execution returns.

```
set\_tabs(tab\_texts[,callback=None])
```

Sets tabs with given names on them in the navigation bar; tab_texts is a list of Unicode strings. When the users navigate between tabs, callback gets called with the index of the active tab as an argument. Tabs can be disabled by giving an empty or one-item tab_texts list.

5.1.5 Form Type

Form implements a dynamically configurable, editable multi-field dialog. Form caters for advanced dialog use cases with requirements such as free selectability of the combination of fields, possibility of validating the user input, and automatically producing the contents of some dialog fields before allowing the closing of the dialog.

```
class Form(fields[, flags=0])
```

Creates a Form instance. fields is a list of field descriptors: (label, type[, value]) where label is a Unicode string

type is one of the following strings: 'text', 'number', 'date', 'time', 'combo' or 'float'

value, depending on type: Unicode string, numeric, float (seconds since Unix epoch rounded down to the nearest local midnight), float (seconds since local midnight), ([choice_label ...], index) of float. For 'float' type the initial value setting might not be shown in the UI.

Form can also be configured and populated after construction. The configuration flags are visible as an attribute. Form implements the list protocol that can be used for setting the form fields, as well as obtaining their values after the dialog has been executed.

Instances of Form type have the following attributes:

flags

This attribute holds the values of the various configuration flags. Currently supported flags are:

FFormEditModeOnly

When this flag is set, the form remains in edit mode while execute runs.

FFormViewModeOnly

When this flag is set, the form cannot be edited at all.

FFormAutoLabelEdit

This flag enables support for allowing the end-users to edit the labels of the form fields.

FFormAutoFormEdit

This flag enables automatic support for allowing the end-users to add and delete the form fields. Note that this is an experimental feature and is not guaranteed to work with all SDK versions

FFormDoubleSpaced

When this flag is set, double-spaced layout is applied when the form is executed: one field takes two lines, as the label and the value field are on different lines.

menu

A list of (title, callback) pairs, where each pair describes an item in the form's menu bar that is active while the dialog is being executed. *title* (Unicode) is the name of the item and *callback* the associated callable object.

save_hook

This attribute can be set to a callable object that receives one argument and returns a Boolean value. It gets called every time the users want to save the contents of an executing Form dialog. A candidate list for new form content - a list representing the currently visible state of the UI - is given as an argument. The list can be modified by <code>save_hook</code>. If <code>save_hook</code> returns <code>True</code>, the candidate list is set as the new contents of the form. Otherwise, the form UI is reset to reflect the field list contained in <code>Form</code> object.

Instances of Form type have the following methods:

execute()

Executes the dialog by making it visible on the UI.

insert(index, field_descriptor)

Inserts the field descriptor into the Form before the given index.

pop()

Removes the last field descriptor from the Form and returns it.

length()

the number of field descriptors in the form.

The subscript notation f[i] can be used to access or modify the i-th element of the form f. Same limitations as discussed above in the context of the flag FFormAutoFormEdit apply to modifying a form while it is executing. The ability to change the schema of a form while it is executing is an experimental feature.

5.1.6 Text Type

Text is a text editor UI control. For examples on the options available with Text, see Figure 5.5.

Instances of Text type have the following attributes:

color

The color of the text. color supports the same color representation models as the graphics module. For the supported color representation models, see Section 5.2.

focus

A Boolean attribute that indicates the focus state of the control. Editor control also takes the ownership of the navigation bar, and this feature is needed to enable the usage of this control in applications that use the navigation bar - for example, navigation tabs.

font

The font of the text. There are two possible ways to set this attribute:

•Using a supported Unicode font, for example u"Latin12". Trying to set a font which is not



Figure 5.5: Examples of the options available for Text type

supported by the device has no effect. A list of supported fonts can be retrieved by using appuifw.available_fonts.

Example, setting font:

```
t = appuifw.Text()
t.font = u"albi17b" # sets font to Albi 17 bold
t.font = u"LatinPlain12" # sets font to Latin Plain 12
```

•Using one of the default device fonts that are associated with the following labels (plain strings): 'annotation', 'title', 'legend', 'symbol', 'dense', 'normal' Example, setting font:

```
t.font = "title" # sets font to the one used in titles
Example, checking the currently set font:
```

```
unicodeFont = t.font
```

The attribute value retrieved is always a Unicode string. If the font has been set with a label, for example, 'title', the attribute will retrieve the font associated with that label.

highlight_color

The highlight color of the text. highlight_color supports the same color representation models as the graphics module. For the supported color representation models, see Section 5.2.

style

The style of the text. The flags for this attribute are defined in the appuifw module. These flags can be combined by using the binary operator |. The flags can be divided into two types: text style and text highlight. Text style flags can be freely combined with each other. However, one or more text style flags can be combined with only one text highlight flag. The flags are:

Text style:

STYLE_BOLD

Enables bold text.

STYLE_UNDERLINE

Enables underlined text.

STYLE_ITALIC

Enables italic text.

STYLE_STRIKETHROUGH

Enables strikethrough.

Text highlight:

${\tt HIGHLIGHT_STANDARD}$

Enables standard highlight.

HIGHLIGHT_ROUNDED

Enables rounded highlight.

HIGHLIGHT_SHADOW

Enables shadow highlight.

Only one highlight is allowed to be used at once. Therefore, it is possible to combine only one highlight with one or more text styles.

Examples:

```
t = appuifw.Text()
# These and other similar values and combinations are valid:
t.style = appuifw.STYLE_BOLD
t.style = appuifw.STYLE_UNDERLINE
t.style = appuifw.STYLE_ITALIC
t.style = appuifw.STYLE_STRIKETHROUGH
t.style = (appuifw.STYLE_BOLD|
   appuifw.STYLE_ITALIC|
   appuifw.STYLE_UNDERLINE)
# These values are valid:
t.style = appuifw.HIGHLIGHT_STANDARD
t.style = appuifw.HIGHLIGHT_ROUNDED
t.style = appuifw.HIGHLIGHT_SHADOW
# This combination is NOT valid:
# Invalid code, do not try!
t.style = (appuifw.HIGHLIGHT_SHADOW|appuifw.HIGHLIGHT_ROUNDED)
```

Instances of Text type have the following methods:

add(text)

Inserts the Unicode string text to the current cursor position.

```
bind(event_code, callback)
```

Binds the callable Python object callback to event event_code. The key codes are defined in the key_codes library module. The call bind(event_code, None) clears an existing binding. In the current implementation the event is always passed also to the underlying native UI control.

clear()

Clears the editor.

```
delete(pos=0, length=len())
```

Deletes length characters of the text held by the editor control, starting from the position pos.

get_pos()

Returns the current cursor position.

len()

Returns the length of the text string held by the editor control.

```
get(|pos=0, length=len()|)
```

Retrieves length characters of the text held by the editor control, starting from the position pos.

Sets the text content of the editor control to Unicode string text.

```
set_pos(cursor_pos)
```

Sets the cursor to *cursor_pos*.

5.1.7 Listbox Type

An instance of this UI control type is visible as a listbox, also known as a list in Symbian, that can be configured to be a single-line item or a double-item listbox. Figure 5.6 shows a single-line item Listbox with icons. For more information on the MBM and MIF formats, see Section 5.1.8.



Figure 5.6: Listbox with icons

class Listbox(list, callback)

Creates a Listbox instance. A callable object *callback* gets called when a listbox selection has been made. list defines the content of the listbox and can be one of the following:

- •A normal (single-line item) listbox: a list of Unicode strings, for example [unicode_string item1, unicode_string item2]
- •A double-item listbox: a two-element tuple of Unicode strings , for example [(unicode_string item1, unicode_string item1description), (unicode_string item2, unicode_string item2description)]
- •A normal (single-line item) listbox with graphics: a two-element tuple consisting of a Unicode string and an Icon object, for example [(unicode_string item1, icon1), (unicode_string item2, icon2)].
- •A double-item listbox with graphics: a three-element tuple consisting of two Unicode strings and one Icon object, for example [(unicode_string item1, unicode_string item1description, icon1), (unicode_string item2, unicode_string item2description, icon2)]

Example: To produce a normal (single-line item) listbox with graphics:

Instances of Listbox type have the following methods:

bind(event_code, callback)

Binds the callable Python object *callback* to event *event_code*. The key codes are defined in the key_codes library module. The call bind(event_code, None) clears an existing binding. In the current implementation the event is always passed also to the underlying native UI control.

current()

Returns the currently selected item's index in the Listbox.

```
set\_list(list[, current])
```

Sets the Listbox content to a list of Unicode strings or a list of tuples of Unicode strings. The accepted structures of *list* are the same as in the Listbox constructor. The optional argument current is the index of the focused list item.

5.1.8 Icon Type

An instance of Icon type encapsulates an icon to be used together with a Listbox instance. Note that currently Icon can only be used with Listbox (see Section 5.1.7).

MBM is the native Symbian OS format used for pictures. It is a compressed file format where the files can contain several bitmaps and can be referred to by a number. An .mbg file is the header file usually associated with an .mbm file, which includes symbolic definitions for each bitmap in the file. For example, an 'avkon.mbm' file has an associated index file called 'avkon.mbg', which is included in S60 SDKs. For more information on the MBM format and the bitmap converter tool, see [4] and search the topics with the key term "How to provide Icons"; this topic also points you to the Bitmap Converter tool that can be used for converting bitmaps into the MBM format.

S60 2^{nd} Edition FP3 introduces a new format for icons called Multi-Image File (MIF). This format is very similar to the MBM format and also contains several compressed files. The files to be compressed should be in Scalable Vector Graphics Tiny (SVG-T) format. For more information on the SVG format, see Scalable Vector Graphics (SVG) 1.1 Specification [10].

class Icon(filename, bitmap, bitmapMask)

Creates an icon. *filename* is a Unicode file name and must include the whole path. Note that MBM and MIF (MIF only in S60 2nd Edition FP3) are the only file formats supported. *bitmap* and *bitmapMask* are integers that represent the index of the icon and icon mask inside that file respectively.

Example: The following builds an icon with the standard signal symbol:

```
icon = appuifw.Icon(u"z:\\system\\data\\avkon.mbm", 28, 29)
```

5.1.9 Content_handler Type

An instance of Content_handler handles data content by its MIME type.

```
class Content_handler([callback])
```

Creates a Content_handler instance. A Content_handler handles data content by its MIME type. The optional *callback* is called when the embedded handler application started with the open method finishes.

Instances of Content_handler type have the following methods:

open(filename)

Opens the file *filename* (Unicode) in its handler application if one has been registered for the particular MIME type. The handler application is embedded in the caller's thread. The call to this function returns immediately. When the handler application finishes, the *callback* that was given to the Content_handler constructor is called.

open_standalone(filename)

Opens the file *filename* (Unicode) in its handler application if one has been registered for the particular MIME type. The handler application is started in its own process. The call to this function returns immediately. Note that *callback* is not called for applications started with this method.

5.1.10 Canvas Type

Canvas is a UI control that provides a drawable area on the screen and support for handling raw key events. Canvas supports the standard drawing methods that are documented in Section 5.2.

```
{\bf class} \ {\bf Canvas} ( \left \lceil redraw\_callback=None, \ event\_callback=None, \ resize\_callback=None \right \rceil )
```

Constructs a Canvas. The optional parameters are callbacks that are called when specific events occur.

Note: Watch out for cyclic references here. For example, if the callbacks are methods of an object that holds a reference to the Canvas, a reference cycle is formed that must be broken at cleanup time or the Canvas will not be freed.

redraw_callback is called whenever a part of the Canvas has been obscured by something, is then

revealed, and needs to be redrawn. This can typically happen, for example, when the user switches away from the Python application and back again, or after displaying a pop-up menu. The callback takes as its argument a four-element tuple that contains the top-left and the bottom-right corner of the area that needs to be redrawn. In many cases redrawing the whole Canvas is a reasonable option.

event_callback is called whenever a raw key event is received. There are three kinds of key events: EEventKeyDown, EEventKey, and EEventKeyUp. When a user presses a key down, events EEventKeyDown and EEventKey are generated. When the key is released, an EEventKeyUp event is generated.

The argument to the event_callback is a dictionary that contains the following data for key events:

- •'type': one of EEventKeyDown, EEventKey, or EEventKeyUp
- •'keycode': the keycode of the key
- •'scancode': the scancode of the key
- •'modifiers': the modifiers that apply to this key event

Each key on the keyboard has one or more scancodes and zero or more keycodes associated with it. A scancode represents the physical key itself and a keycode is the result of state-related operating system defined processing done on the key. For keys that correspond to a symbol in the current character set of the phone, the keycode is equal to the code of the corresponding symbol in that character set. For example, if you are using the Nokia Wireless Keyboard (SU-8W), pressing the key A will always produce the scancode 65 (ASCII code for an upper case A), but the keycode could be either 65 or 91 (ASCII code for a lower case A) depending on whether or not the Shift key is pressed or Caps Lock is active.

The key_codes module contains definitions for the keycodes and scancodes. See Figure 5.7 for the codes of the most common keys on the phone keypad.

Some keys are handled in a special way:

- •A short press of the Edit key causes it to stay down, meaning that no EEventKeyUp event is sent. The event is only sent after a long press.
- •Detecting presses of the Voice tags key or the Power key is not supported.
- •If the right softkey is pressed, the appuifw.app.exit_key_handler callback is always executed.

There is no way to prevent the standard action of the Hang-up key, the Menu key, the Power key or the Voice tags key from taking place.

resize_callback is called when screen size is changed when the Canvas rect size has been changed. The callback takes as its argument a two-element tuple that contains the new clientRect width and height.

Instances of Canvas type have the following attribute:

size

A two-element tuple that contains the current width and height of the Canvas as integers.

Instances of Canvas type have the same standard drawing methods that are documented in Section 5.2.

5.2 graphics — A graphics related services package

The graphics module provides access to the graphics primitives and image loading, saving, resizing, and transformation capabilities provided by the Symbian OS.

The module is usable from both graphical Python applications and background Python processes. However, background processes have some restrictions, namely that plain string symbolic font names are not



Keycode	Scancode
EKeyLeftSoftkey	EScancodeLeftSoftkey
EKeyYes	EScancodeYes
EKeyMenu	EScancodeMenu
EKey09	EScancode09
EKeyStar	EScancodeStar
EKeyLeftArrow	EScancodeLeftArrow
EKeyUpArrow	EScancodeUpArrow
EKeySelect	EScancodeSelect
EKeyRightArrow	ES cancode Right Arrow
EKeyDownArrow	${\bf ES cancode Down Arrow}$
EKeyRightSoftkey	EScancodeRightSoftkey
EKeyNo	EScancodeNo
EKeyBackspace	EScancodeBackspace
EKeyEdit	EScancodeEdit
EKeyHash	EScancodeHash
	EKeyLeftSoftkey EKeyYes EKeyMenu EKey09 EKeyStar EKeyLeftArrow EKeyUpArrow EKeySelect EKeyRightArrow EKeyDownArrow EKeyRightSoftkey EKeyNo EKeyBackspace EKeyEdit

Figure 5.7: Keycodes and scancodes for phone keys usable from Python applications

supported in background processes since background processes have no access to the UI framework (see also Section 5.2.4).

For an example on using this module, see [6].

Functions Image.open and Image.inspect and Image object methods load, save, resize, and transpose are not available for S60 1st Edition.

5.2.1 Module Level Functions

The following free functions - functions that do not belong to any class - are defined in the graphics module:

screenshot()

Takes a screen shot and returns the image in Image format.

5.2.2 Image Class Static Methods

The following Image class static methods are defined in the graphics module:

Image.new(size[, mode='RGB16'])

Creates and returns a new Image object with the given size and mode. *size* is a two-element tuple. *mode* specifies the color mode of the Image to be created. It can be one of the following:

- •'1': Black and white (1 bit per pixel)
- •'L': 256 gray shades (8 bits per pixel)
- •'RGB12': 4096 colors (12 bits per pixel)
- 'RGB16': 65536 colors (16 bits per pixel)
- 'RGB': 16.7 million colors (24 bits per pixel)

Image.open(filename)

Note: Not supported in S60 1st Edition!

Returns a new Image object (mode RGB16) that contains the contents of the named file. The supported file formats are JPEG and PNG. The file format is automatically detected based on file contents. *filename* should be a full path name.

Image.inspect(filename)

Note: Not supported in S60 1st Edition!

Examines the given file and returns a dictionary of the attributes of the file. At present the dictionary contains only the image size in pixels as a two-element tuple, indexed by key 'size'. filename should be a full path name.

5.2.3 Image Objects

An Image object encapsulates an in-memory bitmap.

Note on asynchronous methods: Methods resize, transpose, save, and load have an optional callback argument. If the callback is not given, the method call is synchronous; when the method returns, the operation is complete or an exception has been raised. If the callback is given, the method calls are asynchronous. If all parameters are valid and the operation can start, the method call will return immediately. The actual computation then proceeds in the background. When it is finished, the callback is called with an error code as the argument. If the given code is 0, the operation completed without errors, otherwise an error occurred.

It is legal to use an unfinished image as a source in a blit operation; this will use the image data as it is at the moment the blit is made and may thus show an incomplete result.

Image objects have the following methods:

```
resize(newsize[, callback=None, keepaspect=0])
```

Note: Not supported in S60 1st Edition!

Returns a new image that contains a resized copy of this image. If *keepaspect* is set to 1, the resize will maintain the aspect ratio of the image, otherwise the new image will be exactly the given size.

If *callback* is given, the operation is asynchronous, and the returned image will be only partially complete until *callback* is called.

```
transpose(direction[, callback=None])
```

Note: Not supported in S60 1st Edition!

Creates a new image that contains a transformed copy of this image. The *direction* parameter can be one of the following:

- •FLIP_LEFT_RIGHT: Flips the image horizontally, exchanging left and right edges.
- •FLIP_TOP_BOTTOM: Flips the image vertically, exchanging top and bottom edges.
- •ROTATE_90: Rotates the image 90 degrees counterclockwise.
- •ROTATE_180: Rotates the image 180 degrees.
- •ROTATE_270: Rotates the image 270 degrees counterclockwise.

If *callback* is given, the operation is asynchronous and the returned image will be only partially complete until *callback* is called.

```
load(filename[, callback=None])
```

Note: Not supported in S60 1st Edition!

Replaces the contents of this Image with the contents of the named file, while keeping the current image mode. This Image object must be of the same size as the file to be loaded.

If *callback* is given, the operation is asynchronous and the loaded image will be only partially complete until *callback* is called. *filename* should be a full path name.

```
save(filename[,callback=None, format=None, quality=75, bpp=24, compression='default'])
Note: Not supported in S60 1st Edition!
```

Saves the image into the given file. The supported formats are JPEG and PNG. If *format* is not given or is set to None, the format is determined based on the file name extension: '.jpg' or '.jpeg' are interpreted to be in JPEG format and '.png' to be in PNG format. *filename* should be a full path name.

When saving in JPEG format, the *quality* argument specifies the quality to be used and can range from 1 to 100.

When saving in PNG format, the bpp argument specifies how many bits per pixel the resulting file should have, and compression specifies the compression level to be used.

Valid values for bpp are:

- •1: Black and white, 1 bit per pixel
- •8: 256 gray shades, 8 bits per pixel
- •24: 16.7 million colors, 24 bits per pixel

Valid values for *compression* are:

- •'best': The highest possible compression ratio, the slowest speed
- •'fast': The fastest possible saving, moderate compression
- •'no': No compression, very large file size
- •'default': Default compression, a compromise between file size and speed

If *callback* is given, the operation is asynchronous. When the saving is complete, the *callback* is called with the result code.

stop()

Stops the current asynchronous operation, if any. If an asynchronous call is not in progress, this method has no effect.

Image objects have the following attribute:

size

A two-element tuple that contains the size of the Image. Read-only.

5.2.4 Common Features of Drawable Objects

Objects that represent a surface that can be drawn on support a set of common drawing methods, described in this section. At present there are two such objects: Canvas from the appuifw module and Image from the graphics module.

Options

Many of these methods support a set of standard options. This set of options is as follows:

- outline: The color to be used for drawing outlines of primitives and text. If None, the outlines of primitives are not drawn.
- fill: The color to be used for filling the insides of primitives. If None, the insides of primitives are not drawn. If pattern is also specified, fill specifies the color to be used for areas where the pattern is white.
- width: The line width to be used for drawing the outlines of primitives.
- pattern: Specifies the pattern to be used for filling the insides of primitives. If given, this must be either None or a 1-bit (black and white) Image.

Coordinate representation

The methods accept an ordered set of coordinates in the form of a coordinate sequence. Coordinates can be of type int, long, or float. A valid coordinate sequence is a non-empty sequence of either

- Alternating x and y coordinates. In this case the sequence length must be even, or
- Sequences of two elements, that specify x and y coordinates.

Examples of valid coordinate sequences:

- (1, 221L, 3, 4, 5.85, -3): A sequence of three coordinates
- [(1,221L),(3,4),[5.12,6]): A sequence of three coordinates
- (1,5): A sequence of one coordinate
- [(1,5)]: A sequence of one coordinate
- [[1,5]]: A sequence of one coordinate

Examples of invalid coordinate sequences:

Invalid code, do not use!

- []: An empty sequence
- (1,2,3): Odd number of elements in a flat sequence
- [(1,2),(3,4),None]: Contains an invalid element
- ([1,2],3,4): Mixing the flat and nested form is not allowed

Color representation

All methods that take color arguments accept the following two color representations:

- A three-element tuple of integers in the range from 0 to 255 inclusive, representing the red, green, and blue components of the color.
- An integer of the form <code>Oxrrggbb</code>, where <code>rr</code> is the red, <code>gg</code> the green, and <code>bb</code> the blue component of the color.

For 12 and 16 bit color modes the color component values are simply truncated to the lower bit depth. For the 8-bit grayscale mode images the color is converted into grayscale using the formula (2*r+5*g+b)/8, rounded down to the nearest integer. For 1-bit black and white mode images the color is converted into black (0) or white (1) using the formula (2*r+5*g+b)/1024.

Examples of valid colors:

• 0xffff00: Bright yellow

 $\bullet\,$ 0x004000: Dark green

• (255,0,0): Bright red

• 0: Black

• 255: Bright blue

• (128,128,128): Medium gray

Examples of invalid colors:

Invalid code, do not use!

• (0,0.5,0.9): Floats are not supported

• '#ff80c0': The HTML color format is not supported

• (-1,0,1000): Out-of-range values

• (1,2): The sequence is too short

• [128,128,192]: This is not a tuple

Font specifications

A font can be specified in two ways: Either as a Unicode string that represents a full font name, such as u'LatinBold19', or as a plain string symbolic name that refers to a font setting currently specified by the UI framework. You can obtain a list of all available fonts with the appuifw module function available_fonts.

The symbolic names for UI fonts are:

- 'normal'
- 'dense'
- 'title'
- 'symbol'
- 'legend'
- 'annotation'

Since background processes have no access to the UI framework, these symbolic names are not supported in them. You need to specify the full font name.

Common Methods of Drawable Objects

line(coordseq[, < options>])

Draws a line connecting the points in the given coordinate sequence. For more information about the choices available for *options*, see Section 5.2.4.

polygon(coordseq[, < options>])

Draws a line connecting the points in the given coordinate sequence, and additionally draws an extra line connecting the first and the last point in the sequence. If a fill color or pattern is specified, the polygon is filled with that color or pattern. For more information about the choices available for *options*, see Section 5.2.4.

rectangle(coordseq[, < options>])

Draws rectangles between pairs of coordinates in the given sequence. The coordinates specify the top-left and the bottom- right corners of the rectangle. The sequence must have an even number of coordinates. For more information about the choices available for *options*, see Section 5.2.4.

ellipse(coordseq[, < options>])

Draws ellipses between pairs of coordinates in the given sequence. The coordinates specify the topleft and bottom-right corners of the rectangle inside which the ellipse is contained. The sequence must have an even number of coordinates. For more information about the choices available for options, see Section 5.2.4.

pieslice(coordseq, start, end[, < options>])

Draws pie slices contained in ellipses between pairs of coordinates in the given sequence. The start and end parameters are floats that specify the start and end points of pie slice as the starting and ending angle in radians. The angle 0 is to the right, the angle pi/2 is straight up, pi is to the left and-pi/2 is straight down. *coordseq* is interpreted the same way as for the ellipse method. For more information about the choices available for *options*, see Section 5.2.4.

arc(coordseq, start, end[, < options>])

Draws arcs contained in ellipses between pairs of coordinates in the given sequence. The start and end parameters are floats that specify the start and end points of pie slice as the starting and ending angle in radians. The angle 0 is to the right, the angle pi/2 is straight up, pi is to the left and-pi/2 is straight down. *coordseq* is interpreted the same way as for the ellipse method. For more information about the choices available for *options*, see Section 5.2.4.

point(coordseq[, < options>])

Draws points in each coordinate in the given coordinate sequence. If the *width* option is set to greater than 1, draws a crude approximation of a circle filled with the outline color in the locations. Note that the approximation is not very accurate for large widths; use the ellipse method if you need a precisely formed circle. For more information about the choices available for *options*, see Section 5.2.4.

$\texttt{clear}(\left[\mathit{color}{=}\mathit{0xffffff}\right])$

Sets the entire surface of the drawable to the given color, white by default.

text(coordseq, text[fill=0, font=u"LatinBold12"])

Draws the given text in the points in the given coordinate sequence with the given color (default value is black) and the given font. The font specification format is described above.

$\verb|blit(image[,target=(0,0), source=((0,0),image.size), mask=None, scale=0]|)|$

Copies the source area from the given *image* to the target area in this drawable. The source area is copied in its entirety if *mask* is not given or is set to None. If the mask is given, the source area is copied where the mask is white. *mask* can be either None or a 1-bit (black and white) Image and must be of the same size as the source image.

target and source specify the target area in this image and the source area in the given source. They are coordinate sequences of one or two coordinates. If they specify one coordinate, it is interpreted as the upper-left corner for the area; if they specify two coordinates, they are interpreted as the top-left and bottom-right corners of the area.

If scale is other than zero, scaling is performed on the fly while copying the source area to the

target area. If scale is zero, no scaling is performed, and the size of the copied area is clipped to the smaller of source and target areas.

Note that a blit operation with scaling is slower than one without scaling. If you need to blit the same Image many times in a scaled form, consider making a temporary Image of the scaling result and blitting it without scaling. Note also that the scaling performed by the blit operation is much faster but of worse quality than the one done by the resize method, since the blit method does not perform any antialiasing.

5.3 camera — Interface for taking photographs

Note: Not available for S60 1st Edition.

The camera module enables taking photographs.

The camera module has the following functions¹:

cameras_available()

Returns the number of cameras available in the device.

image_modes()

Returns the image modes supported in the device as a list of strings, for example: ['RGB12', 'RGB', 'RGB16'].

image_sizes()

Returns the image sizes (resolution) supported in the device as a list of (x, y) tuples, for example: [(640, 480), (160, 120)].

flash modes()

Returns the flash modes available in the device as a list of strings.

max_zoom()

Returns the maximum digital zoom value supported in the device as an integer.

exposure_modes()

Returns the exposure settings supported in the device as a list of strings.

white_balance_modes()

Returns the white balance modes available in the device as a list of strings.

```
{\tt take\_photo([} mode, \ size, \ flash, \ zoom, \ exposure, \ white\_balance, \ position \ ])
```

Takes a photograph and returns the image in Image format (for more information on Image format, see Chapter 5.2 graphics Module). If some other application is using the camera, this operation fails, for example with SymbianError: KErrInUse. The settings listed below describe all settings that are supported by the camera module. You can retrieve the mode settings available for your device by using the appropriate functions listed at the beginning of this chapter.

- mode is the display mode of the image. The default value is 'RGB16'. The following display modes are supported:
 - -'RGB12': 4096 colors (12 bits per pixel)
 - -'RGB16': 65536 colors (16 bits per pixel). Default value, always supported
 - -'RGB': 16.7 million colors (24 bits per pixel)
- size is the resolution of the image. The default value is (640, 480). The following sizes are supported, for example, in Nokia 6630: (1280, 960), (640, 480) and (160, 120).
- flash is the flash mode setting. The default value is 'none'. The following flash mode settings are supported:
 - -'none'

No flash. Default value, always supported

-'auto'

Flash will automatically fire when required

¹Descriptions for some of the values are based on information found in S60 SDK documentation [4]

```
-'forced'
Flash will always fire
-'fill_in'
Reduced flash for general lighting
-'red_eye_reduce'
Red-eye reduction mode
```

- •zoom is the digital zoom factor. It is assumed to be on a linear scale from 0 to the maximum zoom value allowed in the device. The default value is 0, meaning that zoom is not used.
- exposure is the exposure adjustment of the device. Exposure is a combination of lens aperture and shutter speed used in taking a photograph. The default value is 'auto'. The following exposure modes are supported:

```
-'auto'
Sets exposure automatically. Default value, always supported
-'night'
Night-time setting for long exposures
-'backlight'
Backlight setting for bright backgrounds
-'center'
Centered mode for ignoring surroundings
```

•white_balance can be used to adjust white balance to match the main source of light. The term white balance refers to the color temperature of the current light. A digital camera requires a reference point to represent white. It will then calculate all the other colors based on this white point. The default value for white_balance is 'auto' and the following white balance modes are supported:

```
-'auto'
Sets white balance automatically. Default value, always supported
-'daylight'
Sets white balance to normal daylight
-'cloudy'
Sets white balance to overcast daylight
-'tungsten'
Sets white balance to tungsten filament lighting
-'fluorescent'
Sets white balance to fluorescent tube lighting
-'flash'
Sets white balance to flash lighting
```

•position is the camera used if the device, such as Nokia 6680, has several cameras. In Nokia 6680, the camera pointing to the user of the device is located in position 1, whereas the one pointing away from the user is located in position 0. The default position is 0.

5.4 keycapture — Interface for global capturing of key events.

The keycapture module offers an API for global capturing of key events. The keycapture module provides the KeyCapturer object as a tool for listening the events.

The KeyCapturer object uses a callback method to report the key events. The callback method is called each time any of the specified keys is pressed.

Currently the keycapture module does not support capturing separate key-up or key-down events.

5.4.1 Module Level Constants

The following constants are defined in the keycapture module:

all_keys

A list of all key codes defined in the key_codes module.

5.4.2 KeyCapturer objects

KeyCapturer object takes a callback method as a mandatory parameter to its constructor. The callback method must have one single parameter for forwarding the key code of the captured key.

There can be several KeyCapturer objects existing at the same time.

KeyCapturer object has following methods and properties:

kevs

List of keys to be captured. Can be read and written. Example:

```
keys = (key_codes.EkeyUpArrow,)
keys = keycapture.all_keys
```

forwarding

Specifies whether captured key events are forwarded to other applications or not. Either has value 1 or 0. Can be read and written.

start()

Starts the actual capturing of key events.

stop()

Stops the actual capturing of key events.

last_key()

Returns last key code that is captured.

5.5 topwindow — Interface for creating windows that are shown on top of other applications.

The topwindow module offers an API for creating windows that are shown on top of other applications and managing the content of these windows. Images can be inserted into the windows and the background color, visibility, corner type and shadow of the window can be manipulated.

topwindow extension does not provide sophisticated drawing capabilities by any means but rather relies on services provided by the graphics extension: topwindow allows graphics Image objects to be put into the windows that are represented by TopWindow objects.

TopWindow object provides mainly only two services: TopWindow objects can be shown or hidden and Images can be put into the windows. However, several images can be added into one TopWindow object and several TopWindow objects can be created and shown. Since the images can be manipulated using the graphics extension this makes it possible to create many kind of content to the TopWindow objects.

5.5.1 TopWindow objects

class TopWindow()

Create a TopWindow object.

TopWindow objects have the following methods and properties:

show()

Shows the window. The window is not shown until show() is called.

hide()

Hides the window.

add_image(image, position)

Inserts an image object graphics. Image into the window. The position of the image is specified by the (position) parameter. If only the coordinates of the top left corner are specified, like (x1, y1) the image is not resized. If four coordinates are given, like(x1, y1, x2, y2), the image is resized to fit to the specified area. Example:

```
add_image(image, (10,20))
add_image(image, (10,20,20,30))
```

$remove_image(image[,position])$

Removes the image from the window. Mandatory parameter *image* must be a graphics.Image object. Parameter *position* may specify the top-left corner coordinates of the image or the rectangular area of the image. If only *image* parameter is given, all the pictures representing this image object are removed from the window. If both parameters are given, only the picture that matches both parameters is removed.

Example:

```
remove_image(image)
remove_image(image, (10,10))
remove_image(image, (10,10,20,20))
```

position

Specifies the coordinates of the top left corner of the window. Can be read and written. Example:

```
position = (10, 20)
```

size

Specifies the size of the window. Can be read and written. Example:

```
size = (100, 200)
```

images

The images inserted into the window. Defined as a list of tuple objects. Each tuple contains a graphics. Image object and the position of the image. The position may specify the top-left coordinate of the image and optionally also the bottom-right coordinate of the image. Parameter (x,y) specifies the top-left coordinate, but does not resize the image while parameter like (x1,y1,x2,y2) specifies both the top-left and bottom-right coordinates and possibly also resizes the image. Can be read and written. Also see the add_image() and remove_image() methods. Example:

```
images = [(image1,(x1,y1)), (image2,(x1,y1,x2,y2)), (image3,(50,50,100,100))]
```

sets the window content to be 3 images. image2 and image3 are possibly resized while the image1 is not)

shadow

Specifies if the shadow of the window is shown and the length of the shadow. Can be read and written. Setting shadow = 0 makes the shadow invisible.

```
Example: shadow = 5
```

corner_type

Specifies the corner type of the window. Can be read and written. Corner type can be one of the following values:

- •square
- •corner1
- •corner2
- •corner3
- •corner5

Example: corner_type = square

maximum_size

Returns the maximum size of the window as a tuple (width, height). Read only property.

background_color

The background color of the window as an integer (e.g. Oxaabbcc). The two greatest hexadecimal digits specify the red, the next two specify the blue and the last ones specify the green color. Can be read and written.

Example: background_color = Oxffffff (sets the white color)

visible

Can be set to 0 or 1. 1 means that window is visible, 0 means that it is not. Can be read and written. Also see the show and hide methods.

Audio and Communication Services

6.1 audio — An audio related services package

The audio module enables recording and playing audio files and access to device text-to-speech engine. The audio module supports all the formats supported by the device, typically: WAV, AMR, MIDI, MP3, AAC, and Real Audio¹. For more information on the audio types supported by different devices, see the *Forum Nokia* Web site [7] and *S60 Platform* Web site [8].

The following Sound class static methods are defined in the audio module:

Sound.open(filename)

Returns a new initialized Sound object with the named file opened. Note that *filename* should be a full Unicode path name and must also include the file extension, for example u'c:\\foo.wav'.

The following data items are available in audio:

KMdaRepeatForever

Possible value for times parameter in open.

ENotReady

The Sound object has been constructed but no audio file is open.

E0pen

An audio file is open but no playing or recording operation is in progress.

EPlaying

An audio file is playing.

ERecording

An audio file is being recorded.

The following method is available in the audio module:

say(text, prefix=audio.TTS_PREFIX)

Passes the text to the device text-to-speech engine. The default prefix is the text-to-speech prefix "(tts)".

6.1.1 Sound Objects

Note: The method current_volume is not available for S60 1st Edition.

class Sound

Sound objects have the following functions:

```
play([times=1, interval=0, callback=None])
```

Starts playback of an audio file from the beginning. Without the parameters *times* and *interval* it plays the audio file one time. *times* defines the number of times the audio file is played, the default being 1. If the audio file is played several times, *interval* gives the time

¹The dynamically loaded audio codec for the sound file is based on the MIME-type information inside the audio file and file extension.

interval between the subsequent plays in microseconds. The optional callback is called when the end of sound file is reached. Other issues:

- •Calling play(audio.KMdaRepeatForever) will repeat the file forever.
- •If an audio file is played but not stopped before exiting, the Python script will leave audio playing on; therefore stop needs to be called explicitly prior to exit.
- •Currently the module does not support playing simultaneous audio files, calling play to a second Sound instance while another audio file is playing, stops the earlier audio file and starts to play the second Sound instance.
- •Calling play while a telephone call is ongoing plays the sound file to uplink. In some devices the sound file is also played to the device speaker.
- •Calling play when already playing or recording results in RuntimeError. Calling stop prior to play will prevent this from happening.

stop()

Stops playback or recording of an audio file.

record()

Starts recording audio data to a file. If the file already exists, the operation appends to the file. For Nokia devices, WAV is typically supported for recording. For more information on the audio types supported by different devices, see the *Forum Nokia* Web site [7] and *S60 Platform* Web site [8]. Other issues:

- •Calling record while a telephone call is ongoing starts the recording of the telephone call.
- •Calling record when already playing or recording results in RuntimeError. Calling stop prior to record will prevent this from happening.

close()

Closes an opened audio file.

state()

Returns the current state of the Sound type instance. The different states (constants) are defined in the audio module. The possible states² are:

ENotReady

The Sound object has been constructed but no audio file is open.

•EOpen

An audio file is open but no playing or recording operation is in progress.

EPlaying

An audio file is playing.

ERecording

An audio file is being recorded.

max_volume()

Returns the maximum volume of the device.

set_volume(volume)

Sets the volume. If the given volume is negative, then the volume is set to zero which mutes the device. If the volume is greater than max_volume, then max_volume is used.

current_volume()

Returns the current volume set.

duration()

Returns the duration of the file in microseconds.

$set_position(microseconds)$

Set the position for the playhead.

current_position()

Returns the current playhead position in microseconds.

²Descriptions for these options are based on information found in S60 SDK documentation [4].

6.2 telephone — Telephone services

This module provides an API to a telephone.

Since the users of the device can also hang-up the phone explicitly, they might affect the current status of the call. In addition, using this extension in an emulator has no effect since no calls can be connected.

The telephone module has the following functions:

dial(number)

Dials the number set in *number*. *number* is a string, for example u'+358501234567' where '+' is the international prefix, '358' is the country code, '50' is the mobile network code (or the area code), and '1234567' is the subscriber number. If there is an ongoing phone call prior to calling dial from Python, then the earlier call is put on hold and a new call is established. Calling dial multiple times when, for example, the first call has been answered and a line has been established results in subsequent calls not being connected.

hang_up()

Hangs up if a call initiated by dial is in process. If this call has already been finished, SymbianError: KErrNotReady is raised.

6.3 messaging — A messaging services package

The messaging module offers APIs to messaging services. Currently, the messaging module has one function:

```
sms_send(recipient, message)
```

Sends an SMS message with body text message (Unicode) to telephone number recipient (string).

6.4 inbox — Interface to device inbox

The inbox module offers APIs to device inbox. Currently, the inbox module supports only SMS handling and notifications of incoming messages and drafts, sent and outbox folders are not supported.

class Inbox()

Create an Inbox object.

6.4.1 Inbox Objects

Inbox objects have the following functions:

sms_messages()

Returns a list of SMS message IDs in device inbox.

content(sms_id)

Retrieve the SMS message content in Unicode. $\,$

$time(sms_id)$

Retrieve the SMS message time of arrival in seconds since epoch.

address(sms_id)

Retrieve the SMS message sender address in Unicode.

delete(sms_id)

Delete the SMS message from inbox.

unread(()

sms_id) Returns the status (1=unread, 0=read) of the SMS with id.

bind(callable)

Bind a callback to receive new message events in device inbox. When a new message arrives to the

device inbox the callback gets called with the received message ID. The received message can be other than an SMS message.

If the message received is deleted immediately after e.g. checking the message content, the "new message" sound and dialog are not activated. This functionality might be useful in notification type of applications.

Examples:

```
>>> import inbox
>>> i=inbox.Inbox()
>>> m=i.sms_messages()
>>> i.content(m[0])
u'foobar'
>>> i.time(m[0])
1130267365.03125
>>> i.address(m[0])
u'John Doe'
>>> i.delete(m[0])
>>> import inbox
>>> id=0
>>> def cb(id_cb):
... global id
... id=id_cb
. . .
>>> i=inbox.Inbox()
>>> i.bind(cb)
>>> # Send an SMS to your inbox here. The "id" gets updated
>>> i.address(id)
u'John Doe'
>>> i.content(id)
u'print 1'
>>>
```

6.5 location — GSM location information

The location module offers APIs to location information related services. Currently, the location has one function:

```
gsm_location()
```

Retrieves GSM location information: Mobile Country Code, Mobile Network Code, Location Area Code, and Cell ID. A location area normally consists of several base stations. It is the area where the terminal can move without notifying the network about its exact position. mcc and mnc together form a unique identification number of the network into which the phone is logged.

6.5.1 Examples

Here is an example of how to use the location package to fetch the location information:

```
>>> import location
>>> print location.gsm_location()
```

Data Management

7.1 contacts — A contacts related services package

The contacts module offers an API to address book services allowing the creation of contact information databases. The contacts module represents a Symbian contact database as a dictionary-like ContactDb object, which contains Contact objects and which is indexed using the unique IDs of those objects. A Contact object is itself a list-like object, which contains ContactField objects and which is indexed using the field indices. Unique IDs and field indices are integers. The ContactDb object supports a limited subset of dictionary functionality. Therefore, only __iter__, __getitem__, __delitem__, __len__, keys, values, and items are included.

ContactDb objects represent a live view into the database. If a contact is changed outside your Python application, the changes are visible immediately, and conversely any changes you commit into the database are visible immediately to other applications. It is possible to lock a contact for editing, which will prevent other applications from modifying the contact for as long as the lock is held. This can be done in, for example, a contacts editor application when a contact is opened for editing, very much like with the Contacts application in your Nokia device. If you try to modify a contact without locking it for editing, the contact is automatically locked before the modification and released immediately afterwards.

7.1.1 Module Level Functions

The following free functions - functions that do not belong to any class - are defined in the Contact module:

Opens a contacts database and returns a ContactDb object. *filename* should be a full Unicode path name. If *filename* is not given, opens the default contacts database. If *mode* is not given, the database must exist. If *mode* is 'c', the database is created if it does not already exist. If *mode* is 'n', a new, empty database is created, overwriting the possible previous database.

Warning: Using open together with the additional parameters *filename* or *mode* is intended for testing purposes only. Due to S60 SDK functionality, the open method can sometimes be unreliable with these parameters.

7.1.2 ContactDb Object

There is one default contact database, but it is possible to create several databases with the open function.

class ContactDb

ContactDb objects have the following methods:

```
add_contact()
```

Adds a new contact into the database. Returns a Contact object that represents the new contact. The returned object is already locked for modification. Note that a newly created contact will contain some empty default fields. If you do not want to use the default fields for anything, you can ignore them.

find(searchterm)

Finds the contacts that contain the given Unicode string as a substring and returns them as a list

import_vcards(vcards)

Imports the vCard(s) in the given string into the database.

export_vcards(ids)

Converts the contacts corresponding to the ID's in the given tuple ids to vCards and returns them as a string.

keys()

Returns a list of unique IDs of all Contact objects in the database.

compact_required()

Verifies whether compacting is recommended. Returns an integer value indicating either a true or false state. Returns True if more than 32K of space is unused and if this comprises more than 50 percent of the database file, or if more than 256K is wasted in the database file.

compact()

Compacts the database to its minimum size.

$__delitem__(id)$

Deletes the given contact from the database.

field_types()

Returns a list of dictionary objects that contains information on all supported field types. The list contains dictionary objects, which each describe one field type. The most important keys in the dictionary are 'type' and 'location' which together indentify the field type. 'type' can have string values such as 'email_address'. 'location' can have the string values 'none', 'home', or 'work'. Another important key is 'storagetype', which defines the storage type of the field. 'storagetype' can have the string values 'text', 'datetime', 'item_id', or 'binary'. Note that the Contacts extension does not support adding, reading, or modifying fields of any other type than 'text' or 'datetime'. The other content returned by field_types is considered to be advanced knowledge and is not documented here.

7.1.3 Contact Object

A Contact object represents a live view into the state of a single contact in the database. You can access the fields either with a contact's numeric field ID as contact[fieldid], or using the find method. Attempting to modify a contact while it has been locked for editing in another application will raise the exception ContactBusy.

class Contact

Contact objects have the following attributes:

id

The unique ID of this Contact. Read-only.

title

The title of this Contact. Read-only.

Contact objects have the following methods:

begin()

Locks the contact for editing. This prevents other applications from modifying the contact for as long as the lock is held. This method will raise the exception ContactBusy if the contact has already been locked.

commit()

Releases the lock and commits the changes made into the database.

rollback()

Releases the lock and discards all changes that were made. The contact remains in the state it was before begin.

as_vcard()

Returns the contact as a string in vCard format.

$$\verb|add_field(type[, value[, label=field_label][, location=location_spec]]|)|$$

Adds a new field into this Contact. This method raises ContactBusy if the contact has been locked by some other application. *type* can be one of the supported field types as a string. The following field types can be added at present:

- •city
- •company_name
- •country
- •date
- •dtmf_string
- •email_address
- •extended_address
- •fax_number
- •first_name
- •job_title
- •last_name
- •mobile_number
- •note
- •pager_number
- •phone_number
- •po_box
- •postal_address
- •postal_code
- •state
- •street_address
- •url
- •video_number
- •wvid

The following field types are recognized but cannot be created at present:

- •first_name_reading
- •last_name_reading
- •picture
- speeddial
- \bullet thumbnail_image
- •voicetag

All supported field types are passed as strings or Unicode strings, except for 'date' which is a float that represents Unix time. For more information on Unix time, see Section 3.5, Date and Time.

field_label is the name of the field shown to the user. If you do not pass a label, the default label for the field type is used.

location_spec, if given, must be 'home' or 'work'. Note that not all combinations of type and location are valid. The settings of the current contacts database in use determine which ones are valid.

find([type=field_type][, location=field_location])

Finds the fields of this contact that match the given search specifications. If no parameters are given, all fields are returned.

__delitem__(fieldindex)

Deletes the given field from this contact. Note that since this will change the indices of all fields that appear after this field in the contact, and since the ContactField objects refer to the fields by index, old ContactField objects that refer to fields after the deleted field will refer to different fields after this operation.

7.1.4 ContactField Object

A ContactField represents a field of a Contact at a certain index. A ContactField has attributes, some of which can be modified. If the parent Contact has not been locked for editing, modifications are committed immediately to the database. If the parent Contact has been locked, the changes are committed only when commit is called on the Contact.

class ContactField

ContactField objects have the following attributes:

label

The user-visible label of this field. Read-write.

value

The value of this field. Read-write.

type

The type of this field. Read-only.

location

The location of this field. This can be 'none', 'work', or 'home'.

schema

A dictionary that contains some properties of this field. The contents of this dictionary correspond to those returned by the ContactDb method field_types.

7.2 calendar — Access to calendar related services

The calendar module offers an API to calendar services. The calendar module represents a Symbian agenda database as a dictionary-like CalendarDb object, which contains Entry objects and which is indexed using the unique IDs of those objects. There are four types of entry objects: AppointmentEntry, EventEntry, AnniversaryEntry, and TodoEntry.

CalendarDb objects represent a live view into the database. If an entry is changed outside your Python application, the changes are visible immediately, and conversely any changes you commit into the database are visible immediately to other applications.

In addition to entries, there are todo lists which contain todo entries. Todo lists are accessed using the dictionary-like TodoListDict and TodoList objects.

All time parameters use Unix time unless stated otherwise. For more information on Unix time, see Section 3.5, Date and Time.

Figure 7.1 demonstrates the relationships of the calendar module objects.

7.2.1 Module Level Functions

The following free functions - functions that do not belong to any class - are defined in the calendar module:

```
open([filename=None, mode=None])
```

Opens a calendar database and returns a new CalendarDb object.

If filename is None, the default database is opened.

If *filename* is given, it should be a full, absolute path name in Unicode that specifies the calendar database to open.

mode can be:

- •None: Opens an existing calendar database.
- •'c': Opens an existing calendar database, or creates it if it doesn't exist.
- •'n': Creates a new, empty calendar database. If *filename* exists, the previous contents are erased.




Figure 7.1: The calendar module objects

7.2.2 CalendarDb Objects

Calendar entries and todo lists are stored in a calendar database. There is one default calendar database but more calendar databases can be created by invoking open with parameters 'n' or 'c'.

class CalendarDb

CalendarDb objects have the following methods:

add_appointment()

Creates and returns a new appointment entry AppointmentEntry. The entry is not added and saved into the database until Entry.commit is called.

add_event()

Creates and returns a new event entry EventEntry. The entry is not added and saved into the database until Entry.commit is called.

add_anniversary()

Creates and returns a new anniversary entry AnniversaryEntry. The entry is not added and saved into the database until Entry.commit is called.

add_todo()

Creates and returns new todo entry TodoEntry. The entry is not added and saved into the database until Entry.commit is called.

find_instances(start_date, end_date, search_str=u" [,appointments=0,events=0,anniversaries=0,todos=0])

The parameters for this function include the start date, end date, search string, and optional parameters. The optional parameters define the entry types to be included into the search. By default all entry types are included. Returns a list that contains Entry instances found in the search. An instance is a dictionary that contains the entry ID and the datetime value. An entry may have several instances if it is repeated, for example once every week, etc. However, all the returned instances occur on the same day, i.e. on the first day between the start and end datetime values that contains instances. To search all instances between the initial start and end datetime values, you may have to execute several searches and change the start datetime value for each search. A match is detected if the search string is a substring of an entry's content.

$monthly_instances(month, appointments=0, events=0, anniversaries=0, todos=0)$

The parameters for this function include *month* (float) and optional parameters. The optional parameters define the entry types to be returned. Returns a list that contains entry instances

occurring during the specified calendar month.

$daily_instances(day, appointments=0, events=0, anniversaries=0, todos=0)$

The parameters for this function include day (float) and optional parameters. The optional parameters define the entry types to be returned. Returns a list that contains entry instances occurring on the specified day.

add_todo_list(|name=None|)

Creates a new todo list. *name* sets the name of the todo list (Unicode). Returns the ID of the created todo list.

export_vcalendars((int,...))

Returns a vcalendar string that contains the specified entries in vCalendar format. The parameter for this function is a tuple that contains the entry IDs of the exported entries.

import_vcalendars(string)

Imports vcalendar entries, given in the string parameter, to the database. Returns a tuple that contains the unique IDs of the imported entries.

todo_lists

Contains a dictionary-like TodoListDict object for accessing the todo lists of this database.

$__delitem__(id)$

Deletes the given calendar Entry from the database. id is the unique ID of the calendar Entry.

__getitem__(*id*)

Returns a calendar Entry object indicated by the unique ID. The returned object can be one of the following: AppointmentEntry, EventEntry, AnniversaryEntry, or TodoEntry. id is the unique ID of the calendar Entry.

compact()

Compacts the database file. The returned value (integer) indicates the success of compaction; a value other than zero means that the compaction was successful.

7.2.3 Entry Objects

An Entry object represents a live view into the state of a single entry in the database. You can access the entries with an entry's unique ID. If you create a new entry using db.add_appointment etc., it is saved into the database only if you call the entry's commit method. In case an entry is already saved into the database, the autocommit mode is on by default and all the changes are automatically saved into the database, unless you call the entry's begin method. If you call the entry's begin method, the changes are not saved into the database until you call the entry's commit method.

Database entries cannot be locked. In other words, other applications are able to make changes to the database entries you are using (not directly to the EntryObjects you are using, but to their representation in the database) at the same time you are modifying them, even if you use begin and commit methods.

class Entry

Entry objects have the following methods and properties:

content

Sets or returns the entry's content text (Unicode).

commit()

Saves the entry or in case of a new entry adds the entry into the database. Note that this can be called only in case of a new entry, created with db.add_appointment etc., or after begin is called.

rollback()

Undoes the changes made after last commit.

set_repeat(dictionary)

Sets the repeat data of the entry. *dictionary* is a repeat data dictionary that contains all the repeat rules. For more information on repeat rules, see Section 7.3.4, Repeat Rules.

get_repeat()

Returns the repeat data dictionary of the entry.

location

Sets or returns the entry's location data (Unicode), for example meeting room information.

set_time(start[, end])

Sets the start and end datetime values of the entry (floats). If only one parameter is given, the other will have the same value.

In case of events, anniversaries, and todo entries the datetime values are truncated to corresponding date values.

TodoEntries can be made undated with TodoEntry.set_time(None). Making the todo entry undated means removing the start and end date and all the repeat rules.

start_time

The start datetime value (float) of the entry or None if the start datetime of the entry is not set.

end_time

The end datetime value (float) of the entry or None if the end datetime of the entry is not set.

id

The unique ID of the entry.

last_modified

The datetime value (float) of the entry's last modification in universal time.

alarm

The alarm datetime value (float) for the entry. None if alarm is not set. Alternatively removes the alarm if the value is set to None.

Alarms can be set to all Entry types. However, only alarms set to Appointments and Anniversaries will actually cause an alarm; this is similar to the Calendar application in your Nokia device, which allows you to set an alarm only for Meetings and Anniversaries. In addition, alarms set to any entries residing in a database other than the default database do not cause actual alarms either.

priority

The priority of the entry, which can be an integer ranging from 0 to 255. Native Phonebook and Calendar applications in Nokia devices use value 1 for high priority, 2 for normal priority, and 3 for low priority.

${\tt crossed_out}$

The crossed out value of an entry. A value that is interpreted as false means that the entry is not crossed out, whereas a value that is interpreted as true means that the entry is crossed out. Note that TodoEntries must also have a cross-out time while the other entry types cannot have one. If TodoEntry is crossed out using this method, the moment of crossing out is set to the cross-out time of the TodoEntry. See also Section 7.3.3, TodoEntry, cross_out_time.

replication

Sets or returns the entry's replication status, which can be one of the following: 'open', 'private', or 'restricted'.

as_vcalendar()

Returns this entry as a vCalendar string.

AppointmentEntry Objects

${f class}$ AppointmentEntry

AppointmentEntry class contains no additional methods compared to the Entry class from which it is derived.

EventEntry

class EventEntry

EventEntry class contains no additional methods compared to the Entry class from which it is derived.

AnniversaryEntry

class AnniversaryEntry

AnniversaryEntry class contains no additional methods compared to the Entry class from which it is derived.

TodoEntry

TodoEntryobjects represent todo entry types. They have additional properties compared to the Entry class from which they are derived.

class TodoEntry

TodoEntryobjects have the following additional properties:

```
cross_out_time
```

The cross-out date value of the entry. The value can be None meaning that the entry is not crossed out, or the cross-out date (float). The set value must be date (float). Setting a cross-out time also crosses out the entry. See also Section 7.3.3, Entry Object, crossed_out.

todo_list

The ID of the todo list to which this entry belongs.

TodoListDict

TodoListDict objects are dictionary-like objects that enable accessing todo lists.

class TodoListDict

TodoListDict objects have the following property:

```
default_list
```

The ID of the default todo list.

TodoList

TodoList objects are dictionary-like objects that enable accessesing todo lists.

class TodoList

TodoList objects have the following properties:

name

The name of the todo list as a Unicode string.

id

Returns the ID of the todo list as an integer.

7.2.4 Repeat Rules

Repeat rules specify an entry's repeat status, that is, the recurrence of the entry. There are six repeat types:

- daily: repeated daily
- weekly: repeat on the specified days of the week, such as Monday and Wednesday, etc.
- monthly_by_dates: repeat monthly on the specified dates, such as the 15th and 17th day of the month
- monthly_by_days: repeat monthly on the specified days, such as the fourth Wednesday of the month, or the last Monday of the month

- yearly_by_date: repeat yearly on the specified date, such as December 24
- yearly_by_day: repeat yearly on the specified day, such as every third Tuesday of May

There are exceptions to repeat rules. For example, you can specify the datetime value (float) in such a way that the entry is not repeated on a specific day even if the repeat rule would specify otherwise.

You must set the start and end dates (floats) of the repeat. The end date can also be set to None to indicate that the repeating continues forever. You can set interval defining how often the repeat occurs, for example in a daily repeat: 1 means every day, 2 means every second day, etc. You can also set the days specifier which lets you explicitly specify the repeat days; for example in a weekly repeat you can set "days": [0,2] which sets the repeat to occur on Mondays and Wednesdays. If you do not set the days specifier, the repeat days are calculated automatically based on the start date.

You can modify repeat data by calling rep_data = entry.get_repeat(), then making changes to rep_data dictionary, and then calling entry.set_repeat(rep_data).

Repeating can be cancelled by calling entry.set_repeat with a parameter that is interpreted to be false, such as entry.set_repeat(None).

Repeat definition examples:

```
repeat = {"type":"daily", #repeat type
          "exceptions": [exception_day, exception_day+2*24*60*60],
          #no appointment on those days
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1} #interval (1=every day, 2=every second day etc.)
repeat = {"type":"weekly", #repeat type
          "days":[0,1], #which days in a week (Monday, Tuesday)
          "exceptions":[exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every week, 2=every second week etc.)
repeat = {"type":"monthly_by_days", #repeat type
          # appointments on second Tuesday and last Monday of the month
          "days":[{"week":1, "day":1},{"week":4, "day":0}],
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, \#end of the repeat
          "interval":1}
          #interval (1=every month, 2=every second month etc.)
repeat = {"type":"monthly_by_dates", #repeat type
          "days": [0,15],
          # appointments on the 1st and 16th day of the month.
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every month, 2=every second month etc.)
repeat = {"type":"yearly_by_date", #repeat type
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+3*365*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every year, 2=every second year etc.)
repeat = {"type":"yearly_by_day", #repeat type
```

```
# appointments on the second Tuesday of February
"days":{"day":1, "week":1, "month":1},
"exceptions":[exception_day], #no appointment on that day
"start":appt_start_date, #start of the repeat
"end":appt_start_date+3*365*24*60*60, #end of the repeat
"interval":1}
#interval (1=every year, 2=every second year etc.)
```

7.3 calendar for EKA2 — Access to calendar related services

The calendar module offers an API to calendar services. The calendar module represents a Symbian agenda database as a dictionary-like CalendarDb object, which contains Entry objects and which is indexed using the unique IDs of those objects. There are five types of entry objects: AppointmentEntry, EventEntry, AnniversaryEntry, ReminderEntry, and TodoEntry.

CalendarDb objects represent a live view into the database. If an entry is changed outside your Python application, the changes are visible immediately, and conversely any changes you commit into the database are visible immediately to other applications.

All time parameters use Unix time unless stated otherwise. For more information on Unix time, see Section 3.5, Date and Time.

7.3.1 Module Level Functions

The following free functions - functions that do not belong to any class - are defined in the calendar module:

```
open([filename=None, mode=None])
```

Opens a calendar database and returns a new CalendarDb object.

If filename is None, the default database is opened.

If *filename* is given, it should contain drive letter, colon and file's name, but no absolute path. *mode* can be:

- •None: Opens an existing calendar database.
- •'c': Opens an existing calendar database, or creates it if it doesn't exist.
- •'n': Creates a new, empty calendar database. If *filename* exists, the previous contents are erased.

7.3.2 CalendarDb Objects

Calendar entries are stored in a calendar database. There is one default calendar database but more calendar databases can be created by invoking open with parameters 'n' or 'c'.

class CalendarDb

CalendarDb objects have the following methods:

add_appointment()

Creates and returns a new appointment entry AppointmentEntry. The entry is not added and saved into the database until Entry.commit is called.

add_event()

Creates and returns a new event entry EventEntry. The entry is not added and saved into the database until Entry.commit is called.

add_anniversary()

Creates and returns a new anniversary entry AnniversaryEntry. The entry is not added and saved into the database until Entry.commit is called.

add_todo()

Creates and returns new todo entry TodoEntry. The entry is not added and saved into the database until Entry.commit is called.

add_reminder()

Creates and returns new reminder entry ReminderEntry. The entry is not added and saved into the database until Entry.commit is called.

- find_instances(start_date, end_date, search_str=u" | ,appointments=0,events=0,anniversaries=0,todos=0,remi
 The parameters for this function include the start date, end date, search string, and optional
 parameters. The optional parameters define the entry types to be included into the search.
 By default all entry types are included. Returns a list that contains Entry instances found
 in the search. An instance is a dictionary that contains the entry ID and the datetime value.
 An entry may have several instances if it is repeated, for example once every week, etc.
- monthly_instances(month, appointments=0, events=0, anniversaries=0, todos=0, reminders=0)

 The parameters for this function include month (float) and optional parameters. The optional parameters define the entry types to be returned. Returns a list that contains entry instances occurring during the specified calendar month.
- $daily_instances(day, appointments=0, events=0, anniversaries=0, todos=0)$

The parameters for this function include day (float) and optional parameters. The optional parameters define the entry types to be returned. Returns a list that contains entry instances occurring on the specified day.

export_vcalendars((int,...))

Returns a vcalendar string that contains the specified entries in vCalendar format. The parameter for this function is a tuple that contains the entry IDs of the exported entries.

import_vcalendars(string)

Imports vcalendar entries, given in the string parameter, to the database. Returns a list that contains the unique IDs of the imported entries.

__delitem__(id)

Deletes the given calendar Entry from the database. id is the unique ID of the calendar Entry.

__getitem__(id)

Returns a calendar Entry object indicated by the unique ID. The returned object can be one of the following: AppointmentEntry, EventEntry, AnniversaryEntry, ReminderEntry, or TodoEntry. id is the unique ID of the calendar Entry.

7.3.3 Entry Objects

An Entry object represents a live view into the state of a single entry in the database. You can access the entries with an entry's unique ID. If you create a new entry using db.add_appointment etc., it is saved into the database only if you call the entry's commit method. In case an entry is already saved into the database, the autocommit mode is on by default and all the changes are automatically saved into the database, unless you call the entry's begin method. If you call the entry's begin method, the changes are not saved into the database until you call the entry's commit method.

Database entries cannot be locked. In other words, other applications are able to make changes to the database entries you are using (not directly to the EntryObjects you are using, but to their representation in the database) at the same time you are modifying them, even if you use begin and commit methods.

class Entry

Entry objects have the following methods and properties:

content

Sets or returns the entry's content text (Unicode).

commit()

Saves the entry or in case of a new entry adds the entry into the database. Note that this can be called only in case of a new entry, created with db.add_appointment etc., or after begin is called.

rollback()

Undoes the changes made after last commit.

set_repeat(dictionary)

Sets the repeat data of the entry. *dictionary* is a repeat data dictionary that contains all the repeat rules. For more information on repeat rules, see Section 7.3.4, Repeat Rules.

get_repeat()

Returns the repeat data dictionary of the entry.

location

Sets or returns the entry's location data (Unicode), for example meeting room information.

set_time(start[, end])

Sets the start and end datetime values of the entry (floats). If only one parameter is given, the other will have the same value.

In case of events, anniversaries, and todo entries the datetime values are truncated to corresponding date values.

TodoEntries can be made undated with TodoEntry.set_time(None). Making the todo entry undated means removing the start and end date and all the repeat rules.

start_time

The start datetime value (float) of the entry or None if the start datetime of the entry is not set.

end_time

The end datetime value (float) of the entry or None if the end datetime of the entry is not set.

id

The unique ID of the entry.

last_modified

The datetime value (float) of the entry's last modification in universal time.

originating

An integer value indicating if the entry is an originating entry or a modifying entry.

alarm

The alarm datetime value (float) for the entry. None if alarm is not set. Alternatively removes the alarm if the value is set to None.

Alarms can be set to all Entry types. However, only alarms set to Appointments and Anniversaries will actually cause an alarm; this is similar to the Calendar application in your Nokia device, which allows you to set an alarm only for Meetings and Anniversaries. In addition, alarms set to any entries residing in a database other than the default database do not cause actual alarms either.

priority

The priority of the entry, which can be an integer ranging from 0 to 255. Native Phonebook and Calendar applications in Nokia devices use value 1 for high priority, 2 for normal priority, and 3 for low priority.

crossed_out

The crossed out value of an entry. Only valid for todo entries. A value that is interpreted as false means that the entry is not crossed out, whereas a value that is interpreted as true means that the entry is crossed out. Note that TodoEntries must also have a cross-out time. If TodoEntry is crossed out using this method, the moment of crossing out is set to the cross-out time of the TodoEntry. See also Section 7.3.3, TodoEntry, cross_out_time.

replication

Sets or returns the entry's replication status, which can be one of the following: 'open', 'private', or 'restricted'.

as_vcalendar()

Returns this entry as a vCalendar string.

AppointmentEntry Objects

class AppointmentEntry

AppointmentEntry class contains no additional methods compared to the Entry class from which it is derived.

EventEntry

class EventEntry

EventEntry class contains no additional methods compared to the Entry class from which it is derived.

AnniversaryEntry

class AnniversaryEntry

AnniversaryEntry class contains no additional methods compared to the Entry class from which it is derived.

ReminderEntry

class ReminderEntry

ReminderEntry class contains no additional methods compared to the Entry class from which it is derived.

TodoEntry

TodoEntryobjects represent todo entry types. They have additional properties compared to the Entry class from which they are derived.

class TodoEntry

TodoEntryobjects have the following additional properties:

cross_out_time

The cross-out date value of the entry. The value can be None meaning that the entry is not crossed out, or the cross-out date (float). The set value must be date (float). Setting a cross-out time also crosses out the entry. See also Section 7.3.3, Entry Object, crossed_out.

7.3.4 Repeat Rules

Repeat rules specify an entry's repeat status, that is, the recurrence of the entry. There are six repeat types:

- daily: repeated daily
- weekly: repeat on the specified days of the week, such as Monday and Wednesday, etc.
- monthly_by_dates: repeat monthly on the specified dates, such as the 15th and 17th day of the month
- monthly_by_days: repeat monthly on the specified days, such as the fourth Wednesday of the month, or the last Monday of the month
- yearly_by_date: repeat yearly on the specified date, such as December 24
- yearly_by_day: repeat yearly on the specified day, such as every third Tuesday of May

There are exceptions to repeat rules. For example, you can specify the datetime value (float) in such a way that the entry is not repeated on a specific day even if the repeat rule would specify otherwise.

You must set the start and end dates (floats) of the repeat. The end date can also be set to None to indicate that the repeating continues forever. You can set interval defining how often the repeat occurs, for example in a daily repeat: 1 means every day, 2 means every second day, etc. You can also set the days specifier which lets you explicitly specify the repeat days; for example in a weekly repeat you can set "days": [0,2] which sets the repeat to occur on Mondays and Wednesdays. If you do not set the days specifier, the repeat days are calculated automatically based on the start date.

You can modify repeat data by calling rep_data = entry.get_repeat(), then making changes to rep_data dictionary, and then calling entry.set_repeat(rep_data).

Repeating can be cancelled by calling entry.set_repeat with a parameter that is interpreted to be false, such as entry.set_repeat(None).

Repeat definition examples:

```
repeat = {"type":"daily", #repeat type
          "exceptions":[exception_day, exception_day+2*24*60*60],
          #no appointment on those days
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1} #interval (1=every day, 2=every second day etc.)
repeat = {"type":"weekly", #repeat type
          "days":[0,1], #which days in a week (Monday, Tuesday)
          "exceptions":[exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every week, 2=every second week etc.)
repeat = {"type":"monthly_by_days", #repeat type
          # appointments on second Tuesday and last Monday of the month
          "days":[{"week":1, "day":1},{"week":4, "day":0}],
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every month, 2=every second month etc.)
repeat = {"type":"monthly_by_dates", #repeat type
          "days": [0,15],
          # appointments on the 1st and 16th day of the month.
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+30*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every month, 2=every second month etc.)
repeat = {"type":"yearly_by_date", #repeat type
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
          "end":appt_start_date+3*365*24*60*60, #end of the repeat
          "interval":1}
          #interval (1=every year, 2=every second year etc.)
repeat = {"type":"yearly_by_day", #repeat type
          # appointments on the second Tuesday of February
          "days":{"day":1, "week":1, "month":1},
          "exceptions": [exception_day], #no appointment on that day
          "start":appt_start_date, #start of the repeat
```

```
"end":appt_start_date+3*365*24*60*60, #end of the repeat
"interval":1}
#interval (1=every year, 2=every second year etc.)
```

7.4 e32db — Interface to the Symbian native DB

The e32db module provides an API for relational database manipulation with a restricted SQL syntax. For details of DBMS support, see the S60 SDK documentation. For examples on using this module, see [6].

The e32db module defines the following functions:

format_rawtime(timevalue)

Formats timevalue (Symbian time) according to the current system's date/time formatting rules and returns it as a Unicode string.

format_time(timevalue)

Formats timevalue according to the current system's date/time formatting rules and returns it as a Unicode string.

7.4.1 Dbms Objects

class Dbms()

Creates a Dbms object. Dbms objects support basic operations on a database.

Dbms objects have the following methods:

begin()

Begins a transaction on the database.

close()

Closes the database object. It is safe to try to close a database object even if it is not open.

commit()

Commits the current transaction.

compact()

Compacts the database, reclaiming unused space in the database file.

create(dbname)

Creates a database with path dbname.

execute(query)

Executes an SQL query. On success, returns 0 if a DDL (SQL schema update) statement was executed. Returns the number of rows inserted, updated, or deleted, if a DML (SQL data update) statement was executed.

open(dbname)

Opens the database in file *dbname*. This should be a full Unicode path name, for example, u'c:\\foo.db'.

rollback()

Rolls back the current transaction.

7.4.2 DB_view Objects

class Db_view()

Creates a Db_view object. DB_view objects generate rowsets from a SQL query. They provide functions to parse and evaluate the rowsets.

 ${\it Db_view}$ objects have the following methods:

col(column)

Returns the value in *column*. The first column of the rowset has the index 1. If the type of the column is not supported, a TypeError is raised. See Table 7.1 for a list of supported data types.

col_count()

Returns the number of columns defined in the rowset.

col_length(column)

Gets the length of the value in *column*. Empty columns have a length of zero; non-empty numerical and date/time columns have a length of 1. For text columns, the length is the character count, and for binary columns, the length is the byte count.

col_raw(column)

Extracts the value of *column* as raw binary data, and returns it as a Python string. The first column of the rowset has the index 1. See Table 7.1 for a list of supported data types.

col_rawtime(column)

Extracts the value of a date/time column at index *column* as a long integer, which represents the raw Symbian time value. The first column of the rowset has the index 1. See Table 7.1 for a list of the supported data types.

col_type(column)

Returns the numeric type of the given column as an integer from a Symbian-specific list of types. This function is used in the implementation of method col.

count_line()

Returns the number of rows available in the rowset.

first_line()

Positions the cursor on the first row in the rowset.

get_line()

Gets the current row data for access.

is_col_null(column)

Tests whether *column* is empty. Empty columns can be accessed like normal columns. Empty numerical columns return a 0 or an equivalent value, and text and binary columns have a zero length.

next_line()

Moves the cursor to the next row in the rowset.

prepare(db, query)

Prepares the view object for evaluating an SQL select statement. db is a Dbms object and query the SQL query to be executed.

7.4.3 Mapping Between SQL and Python Data Types

See Table 7.1 for a summary of mapping between SQL and Python data types. The col function can extract any value except LONG VARBINARY and return it as the proper Python value. In addition, the col_raw function can extract any column type except LONG VARCHAR and LONG VARBINARY as raw binary data and return it as a Python string.

Inserting, updating, or searching for BINARY, VARBINARY, or LONG VARBINARY values is not supported. BINARY and VARBINARY values can be read with col or col_raw.

7.4.4 Date and Time Handling

The functions col and format_time use Unix time, seconds since January 1, 1970, 00:00:00 UTC, as the time format. Internally the database uses the native Symbian time representation that provides greater precision and range than the Unix time. The native Symbian time format is a 64-bit value that represents microseconds since January 1st 0 AD 00:00:00 local time, nominal Gregorian. BC dates are represented by negative values. Since converting this format to Unix time and back may cause slight round-off errors,

SQL type	Symbian column type (in the	Python type	Supported
	DBMS C++ API)		
BIT	EDbColBit	int	
TINYINT	EDbColInt8		
UNSIGNED TINYINT	EDbColUint8		
SMALLINT	EDbColInt16		
UNSIGNED SMALLINT	EDbColUint16		
INTEGER	EDbColInt32		
UNSIGNED INTEGER	EDbColUint32		
COUNTER	EDbColUint32 (with the TDb-		
	Col::EAutoIncrement attribute)		
BIGINT	EDbColInt64	long	
REAL	EDbColReal32	float	yes
FLOAT			
DOUBLE	EDbColReal64		
DOUBLE PRECISION			
DATE			
TIME	EDbColDateTime	float (or long, with col_	rawtime())
TIMESTAMP			
CHAR(n)	EDbColText	Unicode	
VARCHAR(n)	LDbCorrext		
LONG VARCHAR	EDbColLongText		
BINARY(n)	- EDbColBinary	atn	read only
VARBINARY(n)	LDbColbinary	str	
LONG VARBINARY	EDbColLongBinary	n/a	no

Table 7.1: Mapping between SQL and Python types

you have to use the functions col_rawtime and format_rawtime if you need to be able to handle these values with full precision.

The representation of date and time literals in SQL statements depends on the current system date and time format. Note that the only accepted ordering of day, month, and year is the one that the system is currently configured to use. Dates in other order are rejected. The recommended way to form date/time literals for SQL statements is to use the functions format_time or format_rawtime that format the given date/time values properly according to the current system's date/time format settings.

7.5 e32dbm — DBM implemented using the Symbian native DBMS

The e32dbm module provides a DBM API that uses the native Symbian RDBMS as its storage back-end. The module API resembles that of the gdbm module. The main differences are:

- The firstkey() nextkey() interface for iterating through keys is not supported. Use the "for key in db" idiom or the keys or keysiter methods instead.
- This module supports a more complete set of dictionary features than gdbm
- The values are always stored as Unicode, and thus the values returned are Unicode strings even if they were given to the DBM as normal strings.

7.5.1 Module Level Functions

The e32dbm defines the following functions:

open(dbname[,flags, mode])

Opens or creates the given database file and returns an e32dbm object. Note that dbname should

be a full path name, for example, $u'c:\foo.db'$. Flags can be:

- •'r': opens an existing database in read-only mode. This is the default value.
- •'w': opens an existing database in read-write mode.
- •'c': opens a database in read-write mode. Creates a new database if the database does not exist.
- •'n': creates a new empty database and opens it in read-write mode.

If the character 'f' is appended to flags, the database is opened in *fast mode*. In fast mode, updates are written to the database only when one of these methods is called: sync, close, reorganize, or clear.

Since the connection object destructor calls close, it is not strictly necessary to close the database before exiting to ensure that data is saved, but it is still good practice to call the close method when you are done with using the database. Closing the database releases the lock on the file and allows the file to be reopened or deleted without exiting the interpreter.

If you plan to do several updates, it is highly recommended that you open the database in fast mode, since inserts and updates are more efficient when they are bundled together in a larger transaction. This is especially important when you plan to insert large amounts of data, since inserting records to e32db is very slow if done one record at a time.

7.5.2 e32dbm Objects

The e32dbm objects returned by the open function support most of the standard dictionary methods. The supported dictionary methods are:

- __getitem__
- __setitem__
- __delitem__
- has_key
- update
- __len__
- __iter__
- iterkeys
- iteritems
- itervalues
- get
- setdefault
- pop
- popitem
- clear

These work the same way as the corresponding methods in a normal dictionary.

In addition, e32dbm objects have the following methods:

close()

Closes the database. In fast mode, commits all pending updates to disk. close raises an exception if called on a database that is not open.

reorganize()

Reorganizes the database. Reorganization calls compact on the underlying e32db database file, which reclaims unused space in the file. Reorganizing the database is recommended after several updates.

sync()

In fast mode, commits all pending updates to disk.

Standard Library Support and Extensions

8.1 Support for Python Standard Library

The standard library support in Python for S60 is summarized in Table 8.1. For API descriptions, see [1].

Name	Type	Status	Remarks
_testcapi	PYD	Y	
anydbm	PY	X	DBM API is implemented by PY e32dbm that
			relies on PYD e32db (see Chapter 7.5, e32dbm
			Module)
atexit	PY	X	
base64	PY	X	
bdb	PY	(X)	
binascii	built-in	X	
cmd	PY	(X)	
code	PY	X	
codecs	PY	X	
codeop	PY	X	
сору	PY	X	
copy_reg	PY	X	
cStringIO	built-in	X	
dis	PY	(X)	
errno	built-in	X	
exceptions	built-in	X	
future	PY	X	
httplib	PY	X	
imp	built-in	X	
keyword	PY	X	
linecache	PY	X	
marshal	built-in	X	
math	built-in	X	
${\tt md5}^1$	built-in	X	
mimetools	PY	X	
operator	built-in	X	
os, os.path	PY	X	Wraps built-in e32posix. Limitations dis-
			cussed in Section 3.9, Limitations and Areas
			of Development.
pdb	PY	(X)	
quopri	PY	X	
Name	Type	Status	Remarks

 $^{^{1}\}mathrm{Derived}$ from the RSA Data Security, Inc. MD5 Message-Digest Algorithm.

random	PY	X	
re	PY	X	Uses PY sre as its engine.
repr	PY	X	
rfc822	PY	X	
select	PY	X	A minimal implementation: select is supported only for input from sockets.
socket	PY	X	Requires PYD e32socket. Contains extensions as described in Section 8.2.2, socket Module. Limitations discussed in Section 3.9, Limitations and Areas of Development.
sre	PY	X	Wraps built-in _sre.
string	PY	X	
StringIO	PY	X	
struct	built-in	X	
sys	built-in	X	
thread	built-in	X	Contains extensions as described in Section 8.2.1, thread Module
threading	PY	(X)	
time	built-in	X	
traceback	PY	X	
types	PY	X	
urllib	PY	X	
urlparse(urlsplit only)	PY	X	
uu	PY	X	
warnings	PY	X	
whichdb	PY	X	
xreadlines	built-in	X	
zipfile	PY	X	
zlib	PYD	X	

Table 8.1: Status of library module support.

Table 8.1 uses the following coding for module types:

- PY module is implemented in Python.
- Built-in module is a built-in C/C++ module.
- PYD module is a dynamically loadable C/C++ module.

For support status, the following codes are used:

- X included to the Series 60 Python distribution.
- (X) not included to the Series 60 Python distribution, but works both on phone and SDK.
- Y included only to the SDK distribution.

8.2 Extensions to Standard Library Modules

The following standard modules have been extended.

8.2.1 thread — \$60 extensions to standard thread module

The following function has been added to the standard thread module:

ao_waittid(thread_id)

Synchronizes with the end of the execution of the thread identified by the given *thread_id*. The implementation is based on a Symbian OS active object. For the blocking behavior, see Section 4.1.2, Ao_lock Type.

8.2.2 socket — S60 extensions to standard socket module

Bluetooth (BT) support has been added to the standard socket module. The following related constants and functions are defined:

Note: In release 1.0 the functions bt_advertise_service, bt_obex_receive, and bt_rfcomm_get_available_server_channel incorrectly expected to be given the internal e32socket.socket object as the socket parameter instead of the proper socket object. Now the functions work correctly. The old calling convention is still supported but it is deprecated and may be removed in a future release.

AF BT

Represents the Bluetooth address family.

BTPROTO_RFCOMM

This constant represents the Bluetooth protocol RFCOMM.

R.F.COMM

OBEX

Bluetooth service classes supported by bt_advertise_service.

AUTH

ENCRYPT

AUTHOR

Bluetooth security mode flags.

bt_advertise_service(name, socket, flag, class)

Sets a service advertising the service *name* (Unicode) on local channel that is bound to *socket*. If *flag* is True, the advertising is turned on, otherwise it is turned off. The service class to be advertised is either RFCOMM or OBEX.

$\verb|bt_discover([|address|])|$

Performs the Bluetooth device discovery (if the optional BT device address is not given) and the discovery of RFCOMM class services on the chosen device. Returns a pair: BT device address, dictionary of services, where Unicode service name is the key and the corresponding port is the value.

$\verb|bt_obex_discover([|address|])|$

Same as discover, but for discovery of OBEX class services on the chosen device.

bt_obex_send_file(address, channel, filename)

Sends file filename (Unicode) wrapped into an OBEX object to remote address, channel.

bt_obex_receive(socket, filename)

Receives a file as an OBEX object, unwraps and stores it into *filename* (Unicode). *socket* is a bound OBEX socket.

$\verb|bt_rfcomm_get_available_server_channel(|socket|)|$

Returns an available RFCOMM server channel for socket.

set_security(socket, mode)

Sets the security level of the given bound *socket*. The *mode* is an integer flag that is formed using a binary or operation of one or more of: AUTH (authentication), ENCRYPT, AUTHOR (authorization). Example: set_security(s, AUTH | AUTHOR).

Note: When listening to a Bluetooth socket on the phone, it is necessary to set the security level.

Note: SSL is not supported in S60 1st Edition. SSL client certificates are not supported at all.

For examples on the usage of these functions, see Programming with Python for S60 Platform [6].

Extending and Embedding

9.1 Python/C API Extensions

The native API exported by the interpreter in S60 environment consists of class CSPyInterpreter, Python/C API (see [3]) and and a small set of extensions to Python/C API.

9.1.1 class CSPyInterpreter

The class CSPyInterpreter offers an interface for initializing the interpreter and for running scripts. It exports the following public interface:

The caller of the constructor CSPyInterpreter::NewInterpreterL() may provide its own function aStdioInitFunc for initializing Symbian OS STDLIB's standard I/O descriptors. It gets called with the argument aStdioInitCookie. The CSPyInterpreter class can also be requested to leave STDLIB open at its destruction.

The RunScript method establishes a Python interpreter context and runs the script file whose full path name is in argv[0] with the given argument vector. After completion, it leaves the interpreter context and returns a Symbian error code to indicate success or failure.

The CSPyInterpreter::PrintError method can be used to print current Python exception information to the standard error output.

9.1.2 Extensions to Python/C API

Defined in symbian_python_ext_util.h

PyObject* SPyErr_SetFromSymbianOSErr(int error)

Sets Python exception of type PyExc_SymbianError with the value field set to symbolic name of the Symbian OS enumeration value error and returns NULL. In case error has the special value KErrPython, it assumes that a Python exception has already been set and returns NULL.

The following functions can be used for storing the global data in a module implementation. They are thin wrappers around PyDict_SetItem, PyDict_SetItemString, PyDict_GetItem, PyDict_GetItem, PyDict_DelItem and PyDict_DelItemString, respectively, and can be used in the same way. The data is stored in a special completely global dictionary shared by all modules and threads in the current interpreter.

```
int SPyAddGlobal(PyObject *key, PyObject *value)
int SPyAddGlobalString(char *key, PyObject *value)
PyObject* SPyGetGlobal(PyObject *key)
PyObject* SPyGetGlobalString(char *key)
void SPyRemoveGlobal(PyObject *key)
void SPyRemoveGlobalString(char *key)
```

Defined in python_globals.h

PyThreadState* PYTHON_TLS->thread_state

Current thread state.

Thread state and interpreter lock management must be performed according to the instructions; see [3]. Python for S60 Platform extends the Python/C API by offering a facility for querying the related Python thread state (PYTHON_TLS->thread_state) from the context of the currently running thread. This can be used to re-establish the interpreter context with PyEval_RestoreThread in C/C++ code.

To save/restore the interpreter context:

```
Py_BEGIN_ALLOW_THREADS
/* ...your code... */
Py_END_ALLOW_THREADS
```

To restore/save the interpreter context:

```
PyEval_RestoreThread(PYTHON_TLS-$>$thread_state)
/* ...your code... */
PyEval_SaveThread()
```

Defined in pythread.h

```
int PyThread_AtExit(void(*)())
```

An extension to the standard thread module's C API that can be used for registering thread-specific exit functions. In the main thread calling this function has the same effect as calling Py_AtExit. For more information, see [1].

9.2 Extending Python for S60

The general rules and guidelines for writing Python extensions apply in the S60 Python environment as well; for more information, see [2]. The Python/C API is available, see [3] In addition, for an example on porting a simple extension to S60, see [6].

The issues that need to be considered in the implementation of the extension modules include:

- Preparation of the data structures that make the C/C++ coded extensions visible to the Python interpreter and make it possible to perform calls from Python to C/C++ code
- Conversions between C/C++ representations of the Python objects and object types used in the extension code
- Maintenance of the reference counts of the C/C++ representations of the Python objects
- Passing of exceptions between C/C++ code and Python
- Management of interpreter's thread state and the interpreter lock

In addition to the concerns common for all Python C extensions, the following principles should be considered when implementing new Python interfaces in the S60 environment:

- Maximize the usage of Python's built-in types at the interfaces.
- Related to the above: design interfaces in such a way that information can be passed between them with minimal conversions.
- Convert Symbian operating system exceptions / errors to Python exceptions.
- Unicode strings are used at the interfaces to represent text that gets shown on the GUI. They can be passed to and from Symbian operating system without conversions.
- While performing potentially long-lasting / blocking calls from an extension implementation to services outside the interpreter, the interpreter lock must be released and then re-acquired after the call.
- Rather than always implementing a thin wrapper on top of a Symbian OS facility, consider the actual task for which the script writer needs the particular interface. For example, if the task involves interaction with the users using the GUI, the script writer's interest may well be limited to performing the interaction / information exchange in a way that is compatible with the UI style rather than having full control of the low-level details of the GUI implementation.
- The C/C++ implementation of a Python interface should be optimized for performance and covering access to the necessary features of the underlying Platform. Where necessary, the Python programming interface can be further refined by wrapper modules written in Python.

An extension module is packaged in its own dynamically loadable library that must be installed into '\system\libs' directory and named 'module_name.pyd'. The module initialization function must be exported at ordinal 1. The module identification is based on the filename only. As a special feature of PyS60, an optional module finalizer function may be exported at ordinal 2.

The macro versions of memory-management functions PyMem_MALLOC and PyObject_NEW are not included. Use the functions PyMem_Malloc and PyObject_New instead.

9.2.1 Services for Extensions

S60 Python Platform implements an adaptation layer between S60 UI application framework and script language UI extensions to simplify UI extension development. This API is used by the implementation of the appuifw module but not exported in the current release. Some general utility services for extensions are also provided, see Chapter 9.1.

9.2.2 Example

This extension code snippet demonstrates some of the issues mentioned in this chapter, such as:

- Conversion from Python data types, usage of built-in data types at extension interface, usage of Unicode strings (lines 8-12)
- Maintenance of the reference counts (line 36)
- Passing of exceptions between C/C++ code and Python (line 34)
- Releasing the interpreter lock while performing a blocking call to a service outside the interpreter (lines 29, 31)
- Simplifying the API to the note facility of the Platform

```
01 extern "C" PyObject *
02 note(PyObject* /*self*/, PyObject *args)
03 {
04
     TInt error = KErrNone;
05
     int l_tx, l_ty;
06
     char *b_tx, *b_ty;
07
     if (!PyArg_ParseTuple(args, "u#s#", &b_tx, &l_tx, &b_ty, &l_ty))
80
09
       return NULL;
10
     TPtrC8 stype((TUint8*)b_ty, l_ty);
11
12
     TPtrC note_text((TUint16 *)b_tx, l_tx);
13
     CAknResourceNoteDialog* dlg = NULL;
14
     if (stype.Compare(KErrorNoteType) == 0)
15
16
       dlg = new CAknErrorNote(ETrue);
17
     else if (stype.Compare(KInfoNoteType) == 0)
18
       dlg = new CAknInformationNote(ETrue);
     else if (stype.Compare(KConfNoteType) == 0)
19
20
       dlg = new CAknConfirmationNote(ETrue);
21
     else {
22
       PyErr_BadArgument();
23
       return NULL;
24
25
26
     if (dlg == NULL)
27
       return PyErr_NoMemory();
28
     Py_BEGIN_ALLOW_THREADS
29
30
     TRAP(error, dlg->ExecuteLD(note_text));
31
     {\tt Py\_END\_ALLOW\_THREADS}
32
33
    if (error != KErrNone)
34
       return SPyErr_SetFromSymbianOSErr(error);
35
36
       Py_INCREF(Py_None);
37
       return Py_None;
38
     }
39 }
```

Terms and Abbreviations

The following list defines the terms and abbreviations used in this document:

Term	Definition
AAC; Adaptive	AAC provides basically the same sound quality as MP3 while using a
Audio Coding	smaller bit rate. AAC is mainly used to compress music.
Advertise	Advertise service in Bluetooth makes it known that a certain Bluetooth
	service is available.
AMR	Adaptive Multi-rate Codec file format.
API	Application Programming Interface
Bluetooth	Bluetooth is a technology for wireless communication between devices that
	is based on a low-cost short-range radio link.
BPP	Bits Per Pixel
C STDLIB	Symbian OS's implementation of the C standard library
Dialog	A temporary user interface window for presenting context-specific informa-
	tion to the user, or prompting for information in a specific context.
Discovery	Discovery is a process where Bluetooth finds other nearby Bluetooth devices
	and their advertised services.
DLL	Dynamic link library
GSM; Global	GSM is a digital mobile telephone system that uses a variation of time
System for	division multiple access. It digitizes and compresses data, then sends it
Mobile commu-	down a channel with two other streams of user data, each in its own time
	slot.
	Graphical User Interface
I/O	
ÍΡ	Internet Protocol
MBM; Multi-	The native Symbian OS format used for pictures. MBM files can be gener-
BitMap	ated with the bmconv.exe tool included in the S60 SDK.
MIDI; Musi-	A protocol and a set of commands for storing and transmitting information
cal Instrument	about music.
Digital Interface	
MIF; Multi-	MIF files are similar to MBM files and can contain compressed SVG-T files.
Image File	This file type can be generated with the MifConv.exe tool.
MIME; Multi-	MIME is an extension of the original Internet e-mail protocol that can be
purpose Internet	used to exchange different kinds of data files on the Internet.
Mail Extensions	
MP3	A standard technology and format for compressing a sound sequence into
	a very small file while preserving the original level of sound quality when
	it is played.
OS	Operating System
Real Audio	An audio format developed by Real Networks.
RDBMS	Relational database management system
SMS; Short	SMS is a service for sending messages of up to 160 characters, or 224 charac-
Message System	ters if using a 5-bit mode, to mobile phones that use GSM communication.
(within GSM)	
nication GUI I/O IP MBM; Multi- BitMap MIDI; Musi- cal Instrument Digital Interface MIF; Multi- Image File MIME; Multi- purpose Internet Mail Extensions MP3 OS Real Audio RDBMS SMS; Short Message System	slot. Graphical User Interface input/output Internet Protocol The native Symbian OS format used for pictures. MBM files can be generated with the bmconv.exe tool included in the S60 SDK. A protocol and a set of commands for storing and transmitting information about music. MIF files are similar to MBM files and can contain compressed SVG-T files. This file type can be generated with the MifConv.exe tool. MIME is an extension of the original Internet e-mail protocol that can be used to exchange different kinds of data files on the Internet. A standard technology and format for compressing a sound sequence into a very small file while preserving the original level of sound quality when it is played. Operating System An audio format developed by Real Networks. Relational database management system SMS is a service for sending messages of up to 160 characters, or 224 charac-

Term	Definition
Softkey	Softkey is a key that does not have a fixed function nor a function label
	printed on it. On a phone, selection keys reside below or above on the
	side of the screen, and derive their meaning from what is presently on the
	screen.
SQL	Structured Query Language
SVG, SVG - T ;	XML-based vector graphics format for describing two-dimensional graphics
Scalable Vec-	and graphical applications.
tor Graphics	
(-Tiny)	
Twip	Twips are screen-independent units to ensure that the proportion of screen
	elements are the same on all display systems. A twip is defined as $1/1440$
	of an inch, or $1/567$ of a centimeter.
UI	User Interface
UI control	UI control is a GUI component that enables user interaction and represents
	properties or operations of an object.
WAV	A file format for recording sound, especially in multimedia applications.

BIBLIOGRAPHY

- [1] G. van Rossum, and F.L. Drake, Jr., editor. [Python] Library Reference. Available at http://www.python.org/doc
- [2] G. van Rossum, and F.L. Drake, Jr., editor. Extending and Embedding [the Python Interpreter]. Available at http://www.python.org/doc
- [3] G. van Rossum, and F.L. Drake, Jr., editor. Python/C API [Reference Manual]. Available at http://www.python.org/doc
- [4] S60 SDK documentation, available at http://www.forum.nokia.com/
- [5] Getting Started with Python for S60 Platform, available at http://www.forum.nokia.com/
- [6] Programming with Python for S60 Platform, available at http://www.forum.nokia.com/
- [7] Audio & Video section on the *Forum Nokia* Web site (for Nokia devices), http://www.forum.nokia.com/audiovideo
- [8] Developers section on the S60 Platform Web site (for all S60 devices), http://www.s60.com/
- [9] Python for S60 developer discussion board http://discussion.forum.nokia.com/
- [10] Scalable Vector Graphics (SVG) 1.1 Specification http://www.w3.org/TR/SVG/

Α

Reporting Bugs

In order to improve the quality of Python for S60 the developers would like to know of any deficiencies you find in Python for S60 or its documentation.

Before submitting a report, you will be required to log into SourceForge; this will make it possible for the developers to contact you for additional information if needed. It is not possible to submit a bug report anonymously.

All bug reports should be submitted via the project PyS60 Bug Tracker on SourceForge (http://sourceforge.net/tracker/?group_id=154155). The bug tracker offers a Web form which allows pertinent information to be entered and submitted to the developers.

The first step in filing a report is to determine whether the problem has already been reported. The advantage in doing so, aside from saving the developers time, is that you learn what has been done to fix it; it may be that the problem has already been fixed for the next release, or additional information is needed (in which case you are welcome to provide it if you can!). To do this, search the bug database using the search box near the bottom of the page.

If the problem you're reporting is not already in the bug tracker, go back to the project PyS60 Bug Tracker (http://sourceforge.net/tracker/?group_id=154155). Select the "Submit a Bug" link at the top of the page to open the bug reporting form.

The submission form has a number of fields. The only fields that are required are the "Summary" and "Details" fields. For the summary, enter a *very* short description of the problem; less than ten words is good. In the Details field, describe the problem in detail, including what you expected to happen and what did happen. Be sure to include the version of Python for S60 you used, whether any extension modules were involved and what hardware (the S60 device model or emulator) you were using, including version information of the S60 SDK and your device firmware version as appropriate. You can see the device firmware version by entering *#0000# on the device keypad - please include all information that is shown by this code.

The only other field that you may want to set is the "Category" field, which allows you to place the bug report into a broad category (such as "Documentation" or "Library").

Each bug report will be assigned to a developer who will determine what needs to be done to correct the problem. You will receive an update each time action is taken on the bug.

See Also:

How to Report Bugs Effectively

(http://www-mice.cs.ucl.ac.uk/multimedia/software/documentation/ReportingBugs.html)

Article which goes into some detail about how to create a useful bug report. This describes what kind of information is useful and why it is useful.

Bug Writing Guidelines

(http://www.mozilla.org/quality/bug-writing-guidelines.html)

Information about writing a good bug report. Some of this is specific to the Mozilla project, but describes general good practices.

MODULE INDEX

appuifw, 13audio, 37 $\mathtt{calendar},\,44,\,50$ camera, 31contacts, 41 e32, 9 ${\tt e32db},\,55$ $\mathtt{e32dbm},\,57$ ${\tt graphics},\,24$ $\mathtt{inbox},\,39$ $\verb|keycapture|, 32|$ ${\tt location},\,40$ ${\tt messaging},\,39$ $\mathtt{socket},\,63$ ${\tt sysinfo},\,11$ $\mathtt{telephone},\,39$ $\mathtt{thread},\,63$ ${\tt topwindow},\,33$

INDEX

delitem() (CalendarDb method), 46, 51 delitem() (ContactDb method), 42 delitem() (Contact method), 43 getitem() (CalendarDb method), 46, 51	Listbox method, 22 Text method, 21 blit() (method), 30 body (Application attribute), 16
activate_tab() (Application method), 18 add() (Text method), 21 add_anniversary() (CalendarDb method), 45, 50 add_appointment() (CalendarDb method), 45, 50 add_contact() (ContactDb method), 41 add_event() (CalendarDb method), 45, 50 add_field() (Contact method), 43	bt_advertise_service() (in module socket), 63 bt_discover() (in module socket), 63 bt_obex_discover() (in module socket), 63 bt_obex_receive() (in module socket), 63 bt_obex_send_file() (in module socket), 63 bt_rfcomm_get_available_server_channel()
add_image() (TopWindow method), 34 add_reminder() (CalendarDb method), 51 add_todo() (CalendarDb method), 45, 51 add_todo_list() (CalendarDb method), 46 address() (Inbox method), 39	calendar (extension module), 44, 50 CalendarDb (class in calendar), 45, 50 camera (extension module), 31 cameras_available() (in module camera), 31
AF_BT (data in socket), 63 after() (Ao_timer method), 11 alarm (Entry attribute), 47, 52 all_keys (data in keycapture), 33 AnniversaryEntry (class in calendar), 48, 53	cancel() (Ao_timer method), 11 Canvas (class in appuifw), 23 clear() method, 30 Text method, 21
ao_callgate() (in module e32), 9 Ao_lock (class in e32), 10 ao_sleep() (in module e32), 9 Ao_timer (class in e32), 11	close() Dbms method, 55 e32dbm method, 59 Sound method, 38
ao_waittid() (in module thread), 63 ao_yield() (in module e32), 9 Application (class in appuifw), 16 AppointmentEntry (class in calendar), 47, 53	<pre>col() (Db_view method), 56 col_count() (Db_view method), 56 col_length() (Db_view method), 56 col_raw() (Db_view method), 56</pre>
appuifw (standard module), 13 arc() (method), 30 as_vcalendar() (Entry method), 47, 52 as_vcard() (Contact method), 43 audio (extension module), 37	<pre>col_rawtime() (Db_view method), 56 col_type() (Db_view method), 56 color (Text attribute), 19 commit() Contact method, 42</pre>
AUTH (data in socket), 63 AUTHOR (data in socket), 63 available_fonts() (in module appuifw), 15	Dbms method, 55 Entry method, 46, 51 compact() CalendarDb method, 46
background_color (TopWindow attribute), 35 battery() (in module sysinfo), 11 begin() Contact method, 42 Dbms method, 55	ContactDb method, 42 Dbms method, 55 compact_required() (ContactDb method), 42 Contact (class in contacts), 42 ContactDb (class in contacts), 41
bind() Inbox method, 39	ContactField (class in contacts), 44 contacts (extension module), 41

content() (Inbox method), 39	flash_modes() (in module camera), 31
content (Entry attribute), 46, 51	focus
Content_handler (class in appuifw), 23	Application attribute, 17
corner_type (TopWindow attribute), 34	Text attribute, 19
count_line() (Db_view method), 56	font (Text attribute), 19
create() (Dbms method), 55	Form (class in appuifw), 18
cross_out_time (TodoEntry attribute), 48, 53	format_rawtime() (in module e32db), 55
crossed_out (Entry attribute), 47, 52	format_time() (in module e32db), 55
current() (Listbox method), 22	forwarding (KeyCapturer attribute), 33
current_position() (Sound method), 38	free_drivespace() (in module sysinfo), 11
current_volume() (Sound method), 38	free_ram() (in module sysinfo), 11
(2.2.2.2.2.2))	full_name() (Application method), 18
daily_instances() (CalendarDb method), 46, 51	= · · · · · · · · · · · · · · · · · · ·
Db_view (class in e32db), 55	get() (Text method), 21
Dbms (class in e32db), 55	get_line() (Db_view method), 56
default_list (TodoListDict attribute), 48	get_pos() (Text method), 21
<pre>delete()</pre>	get_repeat() (Entry method), 47, 52
Inbox method, 39	graphics (extension module), 24
Text method, 21	gsm_location() (in module location), 40
dial() (in module telephone), 39	,
display_pixels() (in module sysinfo), 11	hang_up() (in module telephone), 39
display_twips() (in module sysinfo), 11	hide() (TopWindow method), 33
drive_list() (in module e32), 9	highlight_color (Text attribute), 20
duration() (Sound method), 38	HIGHLIGHT_ROUNDED (data in appuifw), 21
	HIGHLIGHT_SHADOW (data in appuifw), 21
e32 (extension module), 9	HIGHLIGHT_STANDARD (data in appuifw), 20
e32db (extension module), 55	
e32dbm (module), 57	Icon (class in appuifw), 23
ellipse() (method), 30	id
ENCRYPT (data in socket), 63	Contact attribute, 42
end_time (Entry attribute), 47, 52	Entry attribute, 47, 52
ENotReady (data in audio), 37	TodoList attribute, 48
Entry (class in calendar), 46, 51	Image.inspect() (in module graphics), 26
EOpen (data in audio), 37	Image.new() (in module graphics), 26
EPlaying (data in audio), 37	Image.open() (in module graphics), 26
ERecording (data in audio), 37	image_modes() (in module camera), 31
EventEntry (class in calendar), 47, 53	image_sizes() (in module camera), 31
execute()	images (TopWindow attribute), 34
Dbms method, 55	imei() (in module sysinfo), 11
Form method, 19	import_vcalendars() (CalendarDb method), 46,
exit_key_handler (Application attribute), 17	51
export_vcalendars() (CalendarDb method), 46,	import_vcards() (ContactDb method), 42
51	in_emulator() (in module e32), 9
export_vcards() (ContactDb method), 42	Inbox (class in inbox), 39
exposure_modes() (in module camera), 31	inbox (extension module), 39
	insert() (Form method), 19
FFormAutoFormEdit (data in appuifw), 19	is_col_null() (Db_view method), 56
FFormAutoLabelEdit (data in appuifw), 19	is_ui_thread() (in module e32), 10
FFormDoubleSpaced (data in appuifw), 19	language (out angion module) 22
FFormEditModeOnly (data in appuifw), 18	keycapture (extension module), 32
FFormViewModeOnly (data in appuifw), 19	keys() (ContactDb method), 42
field_types() (ContactDb method), 42	keys (KeyCapturer attribute), 33
file_copy() (in module e32), 9	KMdaRepeatForever (data in audio), 37
find()	label (ContactField attribute), 44
Contact method, 43	last_key() (KeyCapturer method), 33
ContactDb method, 42	last_modified (Entry attribute), 47, 52
find_instances() (CalendarDb method), 45, 51	len() (Text method), 21
first_line() (Db_view method), 56	length() (Form method), 19
flags (Form attribute), 18	Tongon() (Porm mounou), 13

78 Index

line() (mathed) 20	monligation (Entwy attribute) 47 59
line() (method), 30	replication (Entry attribute), 47, 52
Listbox (class in appuifw), 22	resize() (Image method), 27
load() (Image method), 27	RFCOMM (data in socket), 63
location	ring_type() (in module sysinfo), 11
ContactField attribute, 44	rollback()
Entry attribute, 47, 52	Contact method, 42
extension module, 40	Dbms method, 55
	Entry method, 46, 52
max_ramdrive_size() (in module sysinfo), 11	
max_volume() (Sound method), 38	s60_version_info (data in e32), 10
max_zoom() (in module camera), 31	save() (Image method), 27
maximum_size (TopWindow attribute), 35	save_hook (Form attribute), 19
menu	say() (in module audio), 37
Application attribute, 17	schema (ContactField attribute), 44
Form attribute, 19	screen (Application attribute), 17
messaging (extension module), 39	screenshot() (in module graphics), 26
monthly_instances() (CalendarDb method), 45,	selection_list() (in module appuifw), 16
51	set() (Text method), 21
multi_query() (in module appuifw), 16	set_exit() (Application method), 18
multi_selection_list() (in module appuifw),	set_home_time() (in module e32), 9
16	set_list() (Listbox method), 22
10	set_pos() (Text method), 21
name (TodoList attribute), 48	set_position() (Sound method), 38
next_line() (Db_view method), 56	
note() (in module appuifw), 16	set_repeat() (Entry method), 46, 52
nous (m module appairw), 10	set_security() (in module socket), 63
OBEX (data in socket), 63	set_tabs() (Application method), 18
open()	set_time() (Entry method), 47, 52
Content_handler method, 23	set_volume() (Sound method), 38
Dbms method, 55	shadow (TopWindow attribute), 34
in module calendar, 44, 50	show() (TopWindow method), 33
in module contacts, 41	signal()
	Ao_lock method, 10
in module e32dbm, 57	in module sysinfo, 12
open_standalone() (Content_handler method),	signal_strength() (in module sysinfo), 12
23	size
originating (Entry attribute), 52	Canvas attribute, 24
os_version() (in module sysinfo), 12	Image attribute, 28
mingling() (mathed) 20	TopWindow attribute, 34
pieslice() (method), 30	sms_messages() (Inbox method), 39
play() (Sound method), 37	sms_send() (in module messaging), 39
point() (method), 30	socket (extension module), 63
polygon() (method), 30	Sound (class in audio), 37
pop() (Form method), 19	Sound.open() (in module audio), 37
popup_menu() (in module appuifw), 16	SPyAddGlobal(), 66
position (TopWindow attribute), 34	SPyAddGlobalString(), 66
prepare() (Db_view method), 56	SPyErr_SetFromSymbianOSErr(), 65
priority (Entry attribute), 47, 52	SPyGetGlobal(), 66
pys60_version (data in e32), 9	SPyGetGlobalString(), 66
pys60_version_info (data in e32), 9	SPyRemoveGlobal(), 66
PYTHON_TLS->thread_state, 66	
PyThread_AtExit(), 66	SPyRemoveGlobalString(), 66
	start() (KeyCapturer method), 33
query() (in module appuifw), 15	start_exe() (in module e32), 10
	start_server() (in module e32), 10
record() (Sound method), 38	start_time (Entry attribute), 47, 52
rectangle() (method), 30	state() (Sound method), 38
ReminderEntry (class in calendar), 53	stop()
remove_image() (TopWindow method), 34	Image method, 28
reorganize() (e32dbm method), 59	KeyCapturer method, 33

Index 79

```
Sound method, 38
style (Text attribute), 20
STYLE_BOLD (data in appuifw), 20
STYLE_ITALIC (data in appuifw), 20
STYLE_STRIKETHROUGH (data in appuifw), 20
STYLE_UNDERLINE (data in appuifw), 20
sw_version() (in module sysinfo), 12
sync() (e32dbm method), 59
sysinfo (extension module), 11
take_photo() (in module camera), 31
telephone (extension module), 39
text() (method), 30
thread (extension module), 63
time() (Inbox method), 39
title
    Application attribute, 17
    Contact attribute, 42
todo_list (TodoEntry attribute), 48
todo_lists (CalendarDb attribute), 46
TodoEntry (class in calendar), 48, 53
TodoList (class in calendar), 48
TodoListDict (class in calendar), 48
TopWindow (class in topwindow), 33
topwindow (extension module), 33
total_ram() (in module sysinfo), 11
total_rom() (in module sysinfo), 11
transpose() (Image method), 27
type (ContactField attribute), 44
uid() (Application method), 18
unread() (Inbox method), 39
value (ContactField attribute), 44
visible (TopWindow attribute), 35
wait() (Ao_lock method), 10
white_balance_modes() (in module camera), 31
```

80 Index